

S9856

Simplicity



A



B



A



C



A B

Average

Moins Facile

MISSES' SLEEPWEAR

Suggested Fabrics: Cotton Blends, Cotton Lawns, Crepe de Chine, Poplin, Silky Types.
Interfacing: Lightweight Fusible.

Notions: A: Six 3/4" (1.5cm) buttons. B,C: 1 1/2 yds. (1.5m) of 1/2" (1.3cm) elastic.

Sizes	XS	S	M	L	XL	XXL
	4-6	8-10	12-14	16-18	20-22	24-26
European	30-32	34-36	38-40	42-44	46-48	50-52

BODY MEASUREMENTS: Select pattern size based on body measurements

	XS	S	M	L	XL	XXL	Ins.
Bust	29 1/2-30 1/2	31 1/2-32 1/2	34-36	38-40	42-44	46-48	"
Waist	22-23	24-25	26 1/2-28	30-32	34-37	39-41 1/2	"
Hip-9" below waist	31 1/2-32 1/2	33 1/2-34 1/2	36-38	40-42	44-46	48-50	"
Back-neck to waist	15 1/4-15 1/2	15 3/4-16	16 1/4-16 1/2	16 3/4-17	17 1/4-17 1/2	17 3/4-18	"

	XS	S	M	L	XL	XXL	Yds.
Shirt A	45**	2%	2%	2%	2%	3	"
60**	2	2	2%	2%	2%	2%	"
Interfacing	20"	1%	1%	1%	1%	1%	"
Pants B	45**	2%	2%	2%	2%	3	Yds.
60**	1 3/4	2%	2%	2%	2%	2%	"
Shorts C	45**	1%	1%	1%	1%	1%	Yds.
60**	3/4	3/4	3/4	3/4	1%	1%	"

FINISHED GARMENT MEASUREMENTS (Includes Design and Wearing Ease)

	XS	S	M	L	XL	XXL	Ins.
A Bust	39	41	44 1/2	48 1/2	52 1/2	56 1/2	"
A Waist	39 1/2	41 1/2	45	49	53	57	"
C Hip	36	38	41 1/2	45 1/2	49 1/2	53 1/2	"
Width, lower edge							
Shirt A	40	42	45 1/2	49 1/2	53 1/2	57 1/2	Ins.
Width, each leg							
Pants B	22 1/2	24	26 1/2	28 1/2	31 1/2	33 1/2	Ins.
Shorts C	22 1/2	23 1/2	24 1/2	26 1/2	28 1/2	30 1/2	"
Finished back length from base of neck							
Shirt A	25 1/2	26	26 1/2	27	27 1/2	28	Ins.
Finished side length from waist							
Pants B	40 1/2	41	41 1/2	42	42 1/2	43	Ins.
Shorts C	13 1/2	14	14 1/2	15	15 1/2	16	"

*with nap **without nap

VÊTEMENTS DE NUIT POUR JEUNES FEMMES

Tissus Conseillés: Cotonnades, Linon de coton, Crêpe de chine, Popeline, Tissus soyeux.
Entoilage: Thermocollant léger.

Mercerie: A: 6 boutons de 1.5cm. B,C: 1.5m d'élastique de 1.3cm de large.

Tailles	TP/XS	P/S	M/M	G/L	TG/XL	TTG/XXL
Françaises	32-34	36-38	40-42	44-46	48-50	52-54
Européen	30-32	34-36	38-40	42-44	46-48	50-52

MESURES DU CORPS: Choisissez la taille du patron basée sur les mesures du corps

	XS	S	M	L	XL	XXL
Poitrine	75-77	80-83	87-92	97-102	107-112	117-122
Taille	56-58	61-64	67-71	76-81	87-94	99-105
Hanches (23cm au-dessous de la taille)						
Dos du cou à la taille	80-83	85-88	92-97	102-107	112-117	122-127

	XS	S	M	L	XL	XXL	cm
Chemise A	115cm*	2.4	2.5	2.5	2.6	2.7	"
150cm*	1.8	1.8	1.9	1.9	1.9	1.9	"
Entoilage	51cm	1.0	1.0	1.0	1.1	1.1	"
Pantalon B	115cm*	2.5	2.5	2.5	2.6	2.7	m
150cm*	1.5	2.1	2.1	2.4	2.5	2.5	"
Short C	115cm*	1.0	1.0	1.0	1.1	1.3	m
150cm*	0.6	0.7	0.8	0.8	1.1	1.1	"

MESURES DES VÊTEMENTS FINI (Motif et aisance de port compris)

	XS	S	M	L	XL	XXL	cm
A Poitrine	99	104	113	123	133	144	"
A Taille	100	105	114	124	135	145	"
C Hanches	91	97	105	116	126	136	"
Largeur à l'ourlet							
Chemise A	102	107	116	126	136	146	cm
Largeur, chaque jambe							
Pantalon B	57	61	68	73	79	86	cm
Short C	57	59	63	68	73	78	"
Longueur finie – dos, votre nuque à l'ourlet							
Chemise A	65	66	67	69	70	71	cm
Longueur finie – côté, taille à l'ourlet							
Pantalon B	103	104	105	107	108	109	cm
Short C	34	36	37	38	39	41	"

*avec sens **sans sens



A





B



C

Simplicity®

Thank you for purchasing this Simplicity pattern. We made every effort to provide you with a high quality product.



- 1 Front-A
- 2 Back-A
- 3 Collar Band-A
- 4 Collar-A
- 5 Sleeve-A
- 6 Sleeve Band-A
- 7 Guide for Buttonholes-A
- 8 Front-B,C
- 9 Back-B,C
- 10 Pocket-B
- 11 Casing-B,C
- 12 Elastic Guide for Waist-B,C

General Directions

The Pattern

- SYMBOLS**
- ↔ GRAIN LINE Place on straight grain of fabric parallel to selvage
 - ⇄ PLACE SOLID LINE on fold of fabric.
 - CENTER FRONT OR BACK of garment.
 - ▽ NOTCHES
 - ○ DOTS
 - CUTTING LINE
 - == LENGTHEN OR SHORTEN LINES

SEAM ALLOWANCE: 5/8" (1.5cm) unless otherwise stated is included but not printed on MULTI-SIZE PATTERNS. Mark your size with colored felt tip pen. See chart on tissue for how to use MULTI-SIZE PATTERNS.

ADJUST IF NEEDED
Make adjustments before placing pattern on fabric.

TO LENGTHEN:
Cut pattern between lengthen or shorten lines. Spread pattern evenly, the amount needed and tape to paper.

TO SHORTEN:
At lengthen or shorten lines, make an even pleat taking up amount needed. Tape in place.

When lengthen or shorten lines are not given, make adjustments at lower edge of pattern.

Cutting/Marking

BEFORE CUTTING:
PRESS pattern pieces with a warm dry iron. PRE-SHRINK fabric by pre-washing washables or steam-pressing non-washables.

CIRCLE your cutting layout.

PIN pattern to fabric as shown in Cutting Layouts.

• FOR DOUBLE THICKNESS: Fold fabric with RIGHT sides together.


• FOR SINGLE THICKNESS: Place fabric RIGHT side up.

• FOR PILE, SHADED OR ONE WAY DESIGN FABRICS: Use "with nap" layouts

AFTER CUTTING:
Transfer markings to WRONG side of fabric before removing pattern. Use pin and chalk method or dressmaker's tracing paper and wheel.


To Quick Mark:

- Snip edge of fabric to mark notches, ends of fold lines and center lines.
- Pin mark dots.




Sewing

- SEW garment following **Sewing Directions**.
- PIN or machine-baste seams matching notches.
- STITCH 5/8" (1.5 cm) seams unless otherwise stated.
- PRESS seams open unless otherwise indicated clipping when necessary so seams will lie flat.
- TRIM seams to reduce bulk, as shown below.




SPECIAL CUTTING NOTES


★ If layout shows a piece extending past fold, cut out all pieces except piece that extends.




Open out fabric to single thickness. Cut extending piece on RIGHT side of fabric in position shown.




✱ Mark small arrows along both selvages indicating direction of nap or design. Fold fabric crosswise with RIGHT sides together, and cut along fold (a).



Turn one fabric layer around so arrows on both layers go in the same direction. Place RIGHT sides together (b).



Cutting Layouts




POSITION OF PATTERN PIECES MAY VARY SLIGHTLY ACCORDING TO YOUR PATTERN SIZE


TOP A

USE PIECES 1 2 3 4 5 6

45" (115CM) WITH NAP ALL SIZES




60" (150CM) WITH NAP ALL SIZES



INTERFACING

USE PIECES 3 4 6


20" (51CM) ALL SIZES




PANTS B

USE PIECES 8 9 10 11


45" (115CM) WITH NAP ALL SIZES



60" (150CM) WITH NAP SIZES XS S M



60" (150CM) WITH NAP SIZES L XL XXL






CUTTING LAYOUTS CONTINUED ON PAGE 2

S9856



2 of 4

SHORTS C

USE PIECES 8 9 11

45" (115CM)
WITH NAP
ALL SIZES60" (150CM)
WITH NAP
SIZES XS S M L60" (150CM)
WITH NAP
SIZES XL XXL


SEWING TUTORIALS

Build your skills viewing short, easy-to-follow videos at
[simplicity.com/sewingtutorials](https://www.simplicity.com/sewingtutorials)**Sewing Directions**

FABRIC KEY RIGHT SIDE WRONG SIDE INTERFACING LINING LINING

Read **General Directions** on page 1 before you begin.Sewing methods in **BOLD TYPE** have Sewing Tutorial Video available.
Scan QR CODE to watch videos:**EDGESTITCH** - see "how to edgestitch" video.**REINFORCE** - see **Machine Stitches**: "how to reinforce" video.**STAYSTITCH** - see **Machine Stitches**: "how to do stay-stitching" video.**SLEEVE** - see **Armholes/Sleeves**: "sewing a set in sleeve" video.**SLIP-STITCH** - see **Hand Stitching**: "how to slipstitch" video.**TRIM** - see "how to trim, clip, and layer seams" video.**PATTERN PIECES WILL BE IDENTIFIED BY NUMBERS THE FIRST TIME THEY ARE USED.****STITCH SEAMS WITH RIGHT SIDES TOGETHER UNLESS OTHERWISE STATED.****SHIRT A**

- STAYSTITCH** neck edge of Front (1) 1/2" (1.3cm) from cut edge in direction of arrows.
Stay-stitching will not be shown in the following illustrations.
- Turn front edge to **INSIDE** along foldline for interfacing; press. Baste close to inner edge. (Remove basting when shirt is finished.) Turn front edge to **INSIDE** again along foldline for facing; press. Baste across upper edge. Baste inner edge of facing in place to within 5" (13cm) of lower edge.
- STAYSTITCH** neck edge of Back (2) 1/2" (1.3cm) from cut edge. Stitch back to front sections at shoulders.






- Apply fusible interfacing to **WRONG** side of one Collar Band (3) following manufacturer's directions. Trim corners of fusible interfacing for Collar (4) and apply to **WRONG** side of one collar section.
The remaining collar and collar band sections will be used as facings.
- Clip neck edge to stay-stitching. With **RIGHT** sides together, pin single notched edge of collar band to neck edge, placing inner small dots at shoulder seams, matching centers back and remaining small dots. (Neckband extends 5/8" (1.5cm) beyond front opening edges.)
Stitch neck edge.
TRIM seam; clip curves. Press collar band out; press seam toward band.
- With **RIGHT** sides together and raw edges even, stitch facing to collar, leaving double-notched edges open.
- Turn collar; press.
Machine-baste raw edges together. With **RIGHT** sides together and raw edges even, pin collar (facing side) to neckband, matching centers back, double notches and large dots. Machine-baste.
- Press under 5/8" (1.5cm) on single notched edge of collar band facing; trim to 3/8" (1cm).
With **RIGHT** sides together, pin facing to neck band (over collar), matching centers and small dots. Stitch front and double notched edge.
TRIM seam; clip curves.
- Turn collar band facing to **INSIDE**; press.
Pin pressed edge of facing over seam, placing pins on **OUTSIDE**. On **OUTSIDE**, **EDGESTITCH** all edges of neckband, catching in pressed edge of facing on **INSIDE**.



10. Stitch back to fronts at side seams.**11.** Stitch underarm seam of sleeve (5).

S9856

3 of 4



- 12.** Apply fusible interfacing to **WRONG** side of Sleeve Band (6) sections.
Stitch ends of sleeve band together.
Press under 5/8" (1.5cm) on unnotched edge; trim to 3/8" (1cm).



- 13.** With **RIGHT** sides together and raw edges even, pin sleeve band to lower edge of sleeve, matching seams. Stitch seam.
TRIM. Press seam toward band.

- 14.** Turn sleeve band to **INSIDE** along foldline.
Pin pressed edge of band over seam, placing pins on **OUTSIDE**.
On **OUTSIDE**, **EDGESTITCH** band close to seam, catching in pressed edge of band on **INSIDE**.

- 15.** Turn sleeve **RIGHT** side out. Hold shirt **WRONG** side out with armhole toward you.
With **RIGHT** sides together, pin **SLEEVE** to armhole edge with center small dot at shoulder seam, matching underarm seams, notches and remaining small dots; baste.
Stitch. Stitch again 1/8" (3mm) from first stitching. Trim seam below notches close to stitching.
Press only the seam allowance, shrinking out fullness.

- 16.** Open out lower edge of front along line for facing. Turn facing to **OUTSIDE**. Stitch exactly 1-1/4" (3.2cm) from lower edge of facing. Trim facing close to stitching. Trim shirt to within 5/8" (1.5cm) from inner edge of facing.

- 17.** Turn facing to **INSIDE**, pressing up 1-1/4" (3.2cm) hem.
Press under 1/4" (6mm) on inner raw edge.
Stitch hem close to inner pressed edge between opening edges.
Baste remainder of facing in place along inner edge.

- 18.** On **OUTSIDE**, machine-stitch facing in place as basted. Remove basting.

NOTE: If the pattern has been altered, respace buttonhole markings in buttonhole guide.

- 19.** Make buttonhole in collar band at marking.
To mark buttonholes in **RIGHT** front, place guide for buttonholes (7) along finished edge of shirt, matching centers, as shown. Transfer buttonhole markings to shirt. Make buttonholes at markings.
Lap **RIGHT** front over **LEFT**, matching centers. Sew buttons under buttonholes.













PANTS B OR SHORTS C

- 1. FOR VIEW C** - Stitch Front (8) to Back (9) at inner leg seam.

CONTINUE AS FOLLOWS FOR PANTS B

- 2. POCKETS B** - Apply pockets to side edges of Front (8) and Back (9) as follows:
With **RIGHT** sides together, pin Pocket (10) to pants, matching large dots, having raw edges even.
Stitch in a 3/8" (1cm) seam.

- 3.** Press seam toward pocket, pressing pocket out.
UNDERSTITCH front pocket by stitching through pocket and seam allowance close to seam.



- 4.** Press under 1/4" on long outer edges of front and back vent extensions, as shown.

- 5.** Pin front to back at side seams, matching large dots.
Stitch side seams above large dot for vent opening, leaving an opening between upper large dots for pockets; back-stitch at each large dot to reinforce seam.
Stitch pocket edges together from side seam to upper edge.

- 6.** Pin free side seam edges together below large dot for vent, matching foldlines.
To form vent, machine-baste along foldline below large dot. (The vent is basted closed to achieve a crisp fold after vent is pressed in place.

- 7.** Reinforce inner corner and stitch upper end of vent extensions together as follows:
Starting 1" (2.5cm) above large dot, stitch along seam line to large dot; pivot at large dot and stitch across upper end of vent. Clip back seam allowance to large dot at inner corner, being careful not to clip through stitching.


- 8.** Clip pants back seam allowance at end of pocket.
Press seam allowances open between clips, pressing pocket and vent extensions towards front.
Baste 1/4" (6mm) from upper edge of pocket.
Baste upper end of vent extension in place along stitching.

- 9.** On **OUTSIDE**, stitch front along basting, as shown.
Remove basting from upper end of vent.
TIP: For neat stitching, leave long thread ends; pull to **INSIDE** and knot. You will be connecting this stitching to vertical vent stitching in a later step.

- 10.** Pin front extension to front; press, pressing along foldline.
Turn back vent up and out of the way; pin to back.
Machine-baste front extension close to pressed edge to within 5" (13cm) of lower edge.

- 11.** Stitch front to back at inner leg seams.


- 12.** With **RIGHT** sides together, insert one pant leg **INSIDE** the other.



13. Pin center seam, matching inner leg seams and notches. Stitch. **REINFORCE** seam.


CONTINUE AS FOLLOWS FOR SHORTS C

14. Pin front to back at side seams, matching small and large dots. Stitch side seams above small dot.



15. Press seam open.


16. With **RIGHT** sides together, insert one pant leg **INSIDE** the other.




17. Pin center seam, matching inner leg seams and notches. Stitch. **REINFORCE** seam.

CONTINUE AS FOLLOWS FOR VIEW B, C


18. With **RIGHT** sides together, stitch seams of Casing (11), leaving an opening in **LEFT** side seam between small dots, as shown. Back-stitch at small dots to reinforce seam.




19. Press seams open. Fold casing along foldline, with **WRONG** sides together, having raw edges even. Baste raw edges together.




20. Stitch along stitching line, forming two separate casings. The side with the opening is the underside of the casing.




21. With the underside of casing facing you, pin casing to pants or shorts matching centers and side seams. Stitch along seam line. Stitch again 1/4" (6mm) from first stitching within seam allowance. Trim close to second stitching.




22. Press seam toward pants/shorts, pressing casing out.




23. Cut two pieces of elastic each the length of elastic guide for waist (12).



24. Insert elastic through opening in each casing, working elastic through all rows at same time. This eliminates that tug-of-war that you always have when trying to pull that last piece of elastic through an already bunched up casing. Overlap ends and hold with safety pins. Try on pants/shorts and adjust to fit. Stitch ends of elastic together securely.




25. **SLIPSTITCH** opening edges of each casing together. Distribute fullness evenly. **TIP** - To secure elastic so it won't twist in wearing, stitch through all thicknesses of casing in the groove of each seam.




CONTINUE AS FOLLOWS FOR VIEW B


26. Turn front vent extension to **OUTSIDE** along foldline. Stitch across vent exactly 1-1/4" (3.2cm) above lower edge. Trim vent close to stitching. Trim pant/shorts to within 5/8" (1.5cm) of inner edge of facing. Open out pressed edge on back vent. Turn hem 1-1/4" (3.2cm) to **OUTSIDE**; press under 1/4" (6mm) on inner raw edge, as shown. Stitch ends 1/4" (6mm) from raw edge.



27. Turn front and back vent to **INSIDE**. Press, pressing front vent along foldline and hem 1-1/4" (3.2cm) to **INSIDE**. Press under 1/4" (6mm) on inner raw edge of hem. Stitch back edge of vent close to pressed edge. Baste remainder of front vent in place close to inner pressed edge. Stitch hem close to inner pressed edge between opening edges.




28. On **OUTSIDE**, stitch front vent as basted, connecting to stitching on upper edge of vent and keeping back out of the way. Remove basting. **TIP** - For neat stitching, leave long thread ends. When done stitching, pull to **INSIDE** and knot.




CONTINUE AS FOLLOWS FOR VIEW C

29. Press up 1-1/4" (3.2cm) hem on lower edge of shorts; press under 1/4" (6mm) on inner pressed edge. Turn hem to **OUTSIDE** at slit opening edges. Stitch ends in 5/8" (1.5cm) seams. Trim corners.



30. Turn hem to **INSIDE**, turning in seam allowances on slit opening edges; press. Tuck under raw slit edges to meet crease; press. Hand-baste close to pressed edge, squaring stitches above opening. Stitch hem close to inner pressed edge.



31. On **OUTSIDE**, stitch slit edges as basted; remove basting.



Congrats!

You've completed your sewing adventure

**SHARE
YOUR** LOOK



Post your pattern and tag us
@simplicity_creative_group and **#simplicitypatterns**
for a chance to be featured on our social media.

Look for more PDF patterns at [simplicity.com](https://www.simplicity.com)

Have a question or need help with your sewing project call us at
1-888-588-2700



Simplicity ©2023 a division of IG Design Group Americas Inc. • Atlanta, GA 30342 USA www.thedesigngroup.com • All Rights Reserved. www.simplicity.com • Made in the U.S.A. Fabriqué aux États-Unis.

To be used for individual private home use only and not for commercial or manufacturing purposes. • A usage privé seulement et non à des fins commerciales ou de production en série. • Para uso privado solamente, no se puede utilizar con propósitos de comercialización o de producción en serie.