

S3049

Simplicity

1970s Vintage



easy-to-sew

Easy

MISSES' DRESS, TUNIC AND PANTS

Suggested Fabrics: Bonded Crepe, Cotton Jacquard, Double Knit, Homespun, Linen, Novelty Pique, Polyester Knit, Silk and Worsted, Silk Linen. **Lining:** Lightweight Fabric or Lining Fabric. **Interfacing:** Lightweight Fusible.

Notions: Seam Binding or Stretch Lace. **Dress or Tunic:** One 22" (56cm) zipper, hook and eye. **Pants:** 1½ yds. (1.2m) of ¾" (2cm) elastic.

Sizes	8	10	12	14	16	18	20	22	24	26
European	34	36	38	40	42	44	46	48	50	52

BODY MEASUREMENTS: Select pattern size based on body measurements

Bust	31½	32½	34	36	38	40	42	44	46	48	Ins.
Waist	24	25	26½	28	30	32	34	37	39	41½	"
Hip-9" below waist	33½	34½	36	38	40	42	44	46	48	50	"
Back-neck to waist	15¾	16	16¼	16½	16¾	17	17¼	17¾	17½	17¾	"

Lining - View 1,2,3

45***	½	½	½	½	½	½	½	½	½	¾	¾	Yds.
-------	---	---	---	---	---	---	---	---	---	---	---	------

Interfacing - View 1,2,3

20"	¾ yd.
-----	-------

View 1 - Dress

45**	2½	2½	2½	2½	2½	2½	2½	2½	2½	2½	2½	Yds.
60**	1¾	1¾	1¾	1¾	1¾	1¾	2¼	2¼	2¼	2¼	2½	"

Contrast (Front Yoke, Front Neck Facing, Sleeves)

45**	¾	¾	¾	¾	¾	¾	¾	¾	¾	¾	¾	Yds.
60**	½	½	½	½	½	¾	¾	¾	¾	¾	¾	"

View 2 - Dress

45**	2½	2½	2½	2½	2½	2½	2½	3	3	3	Yds.
60**	1¾	1¾	1¾	1¾	1¾	1¾	2	2¼	2¼	2¾	"

View 3 - Tunic and Pants

45**	3¾	3¾	3¾	4¾	4¾	4¾	4¾	4¾	5	5	Yds.
60**	2¾	2¾	2¾	2¾	2¾	3¾	3¾	3¾	3¾	3¾	"

NOTE: Please refer to the sewing instructions for **FINISHED GARMENT MEASUREMENTS**.

*with nap **without nap

Facile

ROBE, TUNIQUE ET PANTALON POUR JEUNES FEMMES

Tissu Conseillé: Crêpe contrecollés, Jacquard de coton, Tricot double, Tissu homespun, Toile de lin, Piqué fantaisie, Tricot polyester, Soie et peignée, Linge en soie. **Doubleure:** Tissu léger ou tissu à doublure. **Entoilage:** Thermocollant léger.

Mercerie: Extra-fort ou dentelle extensible. **Robe ou tunique:** 1 fermeture à glissière de 56cm, agrafe. **Pantalon:** 1.2m d'élastique de 2cm.

Tailles	8	10	12	14	16	18	20	22	24	26
Françaises	36	38	40	42	44	46	48	50	52	54
Européen	34	36	38	40	42	44	46	48	50	52

MESURES DU CORPS: Choisissez la taille du patron basée sur les mesures du corps

Poitrine	80	83	87	92	97	102	107	112	117	122	cm
Taille	61	64	67	71	76	81	87	94	99	106	"
Hanches (23cm au-dessous de la taille)	85	88	92	97	102	107	112	117	122	127	cm
Dos du cou à la taille	40	40.5	41.5	42	42.5	43	44	44	44.5	44.5	"

Doubleure - Modèle 1,2,3

115cm**	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	0.5	m
---------	-----	-----	-----	-----	-----	-----	-----	-----	-----	-----	---

Entoilage - Modèle 1,2,3

51cm	- 0.3m
------	--------

Modèle 1 - Robe

115cm*	2.2	2.3	2.3	2.3	2.3	2.3	2.3	2.3	2.4	2.4	m
150cm*	1.3	1.3	1.3	1.4	1.5	1.7	2.1	2.1	2.1	2.3	"

Contraste (Empiècement devant, Parementure d'encolure devant, Manches)

115cm*	0.6	0.6	0.6	0.7	0.7	0.7	0.7	0.7	0.7	0.7	m
150cm*	0.5	0.5	0.5	0.5	0.5	0.5	0.6	0.6	0.6	0.6	"

Modèle 2 - Robe

115cm*	2.2	2.3	2.4	2.4	2.6	2.6	2.6	2.6	2.7	2.7	m
150cm*	1.5	1.6	1.6	1.7	1.7	1.7	1.8	2.1	2.1	2.5	"

Modèle 3 - Tunique et pantalon


115cm*	3.4	3.4	3.5	3.8	4.3	4.3	4.5	4.5	4.5	4.6	m
150cm*	2.5	2.5	2.6	2.6	2.6	3.4	3.4	3.4	3.5	3.5	"

NOTE: S'il vous plaît, reportez-vous aux instructions de couture pour les **MESURES DU VÊTEMENTS FINI**.


*avec sens **sans sens



1




2



3



3



How to use your Simplicity Pattern

Read all directions carefully before beginning to work

1. Prepare your pattern

Select the pattern pieces for the view you plan to make from the box to the left. Do not cut away margins.

This pattern is made to body measurements with ease allowed for style, fit and comfort. Check your back waist and dress length. If necessary, alter the pattern before placing it on fabric. Lengthening and shortening lines are indicated on pattern.

TO LENGTHEN: Cut pattern between printed lines. Place paper underneath. Spread pattern the necessary amount and pin to paper.

TO SHORTEN: At the printed line, pin a pleat half the amount to be shortened (i.e. 1/2" deep to shorten 1").

See Simplicity Sewing Book for other pattern alterations.

2. Prepare your fabric

Press fabric. Unless fabric is pre-shrunk, shrink before cutting.

STRAIGHTEN ENDS: Clip one selvage and tear fabric or pull a crosswise thread and cut across fabric.

STRAIGHTEN UNEVEN GRAIN: Pull fabric on the bias in opposite direction until crosswise threads are straight and squared with selvages. **This cannot be done on permanent finish fabrics.**

3. Know your pattern markings

STRAIGHT GRAIN: Place an even distance from selvage or a straight thread.

FOLD GRAIN: Place on fold of fabric.

CUTTING LINE

LENGTHENING AND SHORTENING LINES

STITCHING LINES: For darts, seams, etc.

SEAM ALLOWANCE: 5/8" unless otherwise stated.

NOTCHES: Blocked in for easier cutting; match notches with same numbers.

4. Laying out and cutting your pattern

Circle cutting layout for View, Size and Fabric width.

FOR DOUBLE THICKNESS: Fold fabric with RIGHT side INSIDE and place pattern on WRONG side of fabric.

FOR SINGLE THICKNESS: Place pattern on RIGHT side of fabric.

FOR NAP OR ONE WAY DESIGN FABRICS: Use "with nap" cutting layout.

Before cutting, place all pattern pieces on fabric, following cutting layouts. Margins may overlap.

When pattern is placed with printed side up, it is shown in white.

When pattern is placed with printed side down, it is shown shaded.

Solid outline indicates fabric to be cut without a pattern piece.

Cut thru pattern and fabric on cutting lines; cut notches out from cutting lines.

5. Mark your fabric

Before removing pattern, transfer markings to WRONG side of fabric with tracing wheel and dressmaker's tracing paper.

FOR SINGLE THICKNESS: Place one sheet of tracing paper face up under WRONG side of fabric.

FOR DOUBLE THICKNESS: Place one sheet of tracing paper face up under fabric; place another sheet face down under pattern.

See Simplicity Sewing Book for "chalk-marking" and Tailor's-tacks.

Do not remove pattern from fabric until you are ready to sew.

6. Sewing your garment

READ DIRECTIONS on pattern pieces as you work.

STAY-STITCH: Machine-stitch thru single thickness of fabric to prevent stretching of bias or curved edges—done on seam line or 1/8" from seam line within seam allowance.

Stay-stitching is shown only the first time a section of garment is illustrated.

PIN or BASTE SEAMS: Match notch 1 to 2, 2 to 2, etc. (Baste by hand or machine using a long stitch.)

STITCH SEAMS: In direction shown by arrows on pattern.

PRESS SEAMS: Open, unless otherwise stated.

See Simplicity Sewing Book for additional sewing details.


DISREGARD ANY PERFORATIONS ON TISSUE PATTERN PIECES

cutting layouts

Black area represents fabric

view 1 dress

35" 36" fabric without nap all sizes



44" 45" fabric without nap sizes 8, 10



44" 45" fabric without nap size 12



44" 45" fabric without nap sizes 14, 16, 18



58" 60" fabric without nap all sizes



view 1 contrasting yoke front and sleeves

35" 36" fabric without nap all sizes



58" 60" fabric without nap all sizes




view 2 dress

35" 36" fabric without nap sizes 8, 10



35" 36" fabric without nap sizes 12, 14, 16, 18



44" 45" fabric without nap sizes 8, 10



44" 45" fabric without nap size 12




44" 45" fabric without nap size 14




44" 45" fabric without nap sizes 16, 18




58" 60" fabric without nap sizes 8, 10



58" 60" fabric without nap sizes 12, 14




58" 60" fabric without nap sizes 16, 18




view 3 tunic and pants

35" 36" fabric without nap sizes 8, 10




35" 36" fabric without nap sizes 12, 14, 16, 18




44" 45" fabric without nap sizes 8, 10




44" 45" fabric without nap sizes 12, 14, 16, 18



58" 60" fabric without nap sizes 8, 10, 12



58" 60" fabric without nap size 14



58" 60" fabric without nap sizes 16, 18



view 1 2 3 yoke lining view 1 2 3 neck interfacing

35" 36" 44" 45" lightweight fabric without nap all sizes




NOTE: Neck Interfacing - Cut 1 on fold by E and 2 by F, less 3/8" on long unnotched edge.

25" 32" 35" 36" fabric all sizes



Thank you for purchasing this Simplicity pattern.
We made every effort to provide you with a high quality product.

SUPPLEMENTAL CUTTING LAYOUTS




- A FRONT
- B FRONT FACING
- C YOKE FRONT
- D BACK
- E FRONT NECK FACING
- F BACK NECK FACING
- G SLEEVE VIEW 1
- H ARMHOLE FACING VIEWS 2, 3
- K PANTS FRONT VIEW 3
- L PANTS BACK VIEW 3

Sizes	8	10	12	14	16	18	20	22	24	26
European	34	36	38	40	42	44	46	48	50	52

FINISHED GARMENT MEASUREMENTS (Includes Design and Wearing Ease)

View	1, 2, 3 Bust	31½	32½	34	36	38	40	42	44	46	48	50	52
View 1, 2, 3 Bust	34	35	36½	38½	40½	42½	44½	46½	48½	50½	52	54	56
View 1, 2, 3 Waist	31½	32½	34	36	38	40	42	44	46	48	50	52	54
Width, lower edge													
View 1, 2 Dress	51	52	53½	55½	57½	59½	61½	63½	65½	67½	69½	71½	73½
View 3 Dress	45	46	47½	49½	51½	53½	55½	57½	59½	61½	63½	65½	67½
Finished back length from base of neck													
View 1, 2 Dress	41¾	41¾	41¾	42	42¾	42¾	42¾	43	43¾	43¾	43¾	44	44
View 3 Tunic	32¾	32¾	32¾	33	33¾	33¾	33¾	34	34¾	34¾	34¾	35	35
Finished back length from waist													
View 1, 2 Dress	39¾	40	40¾	40¾	40¾	41	41¾	41¾	41¾	42	42	42	42

Cutting Layouts




POSITION OF PATTERN PIECES MAY VARY SLIGHTLY ACCORDING TO YOUR PATTERN SIZE

LINING - VIEW 1, 2, 3

USE PIECE C


45" (115CM)
WITHOUT NAP
ALL SIZES



INTERFACING - VIEW 1, 2, 3

USE PIECES E F


20" (51CM)
ALL SIZES




VIEW 1 - DRESS

USE PIECES A B D F

45" (115CM)
WITHOUT NAP
ALL SIZES




60" (150CM)
WITH NAP
ALL SIZES



CONTRAST (FRONT YOKE, FRONT NECK FACING, SLEEVES)

USE PIECES C E G

45" (115CM)
WITH NAP
ALL SIZES




General Directions

The Pattern

- SYMBOLS**
- GRAIN LINE Place on straight grain of fabric parallel to selvage
 - PLACE SOLID LINE on fold of fabric.
 - CENTER FRONT OR BACK OF GARMENT.
 - NOTCHES
 - DOTS
 - CUTTING LINE
 - LENGTHEN OR SHORTEN LINES

SEAM ALLOWANCE: 5/8" (1.5cm) unless otherwise stated is included but not printed on MULTI-SIZE PATTERNS. Mark your size with colored felt tip pen. See chart on tissue for how to use MULTI-SIZE PATTERNS.

ADJUST IF NEEDED
Make adjustments before placing pattern on fabric.



TO LENGTHEN: Cut pattern between lengthen or shorten lines. Spread pattern evenly, the amount needed and tape to paper.

TO SHORTEN: At lengthen or shorten lines, make an even pleat taking up amount needed. Tape in place.

When lengthen or shorten lines are not given, make adjustments at lower edge of pattern.

Cutting/Marking


BEFORE CUTTING:
PRESS pattern pieces with a warm dry iron. PRE-SHRINK fabric by pre-washing washables or steam-pressing non-washables.

CIRCLE your cutting layout.
PIN pattern to fabric as shown in Cutting Layouts.

- FOR DOUBLE THICKNESS: Fold fabric with RIGHT sides together.
- FOR SINGLE THICKNESS: Place fabric RIGHT side up.
- FOR PILE, SHADED OR ONE WAY DESIGN FABRICS: Use "with nap" layouts


AFTER CUTTING:
Transfer markings to WRONG side of fabric before removing pattern. Use pin and chalk method or dressmaker's tracing paper and wheel.

- To Quick Mark:**
- Snip edge of fabric to mark notches, ends of fold lines and center lines.
 - Pin mark dots.




Sewing

- SEW garment following Sewing Directions.
- PIN or machine-baste seams matching notches.
- STITCH 5/8" (1.5 cm) seams unless otherwise stated.
- PRESS seams open unless otherwise indicated clipping when necessary so seams will lie flat.
- TRIM seams to reduce bulk, as shown below.




SPECIAL CUTTING NOTES

★ If layout shows a piece extending past fold, cut out all pieces except piece that extends.




Open out fabric to single thickness. Cut extending piece on RIGHT side of fabric in position shown.


✱ Mark small arrows along both selvages indicating direction of nap or design. Fold fabric crosswise with RIGHT sides together, and cut along fold (a).



Turn one fabric layer around so arrows on both layers go in the same direction. Place RIGHT sides together (b).




60" (150CM)
WITH NAP
ALL SIZES



VIEW 2 - DRESS


USE PIECES A B C D E F H

45" (115CM)
WITH NAP
SIZES 8 10 12 14




45" (115CM)
WITH NAP
SIZES 16 18 20 22 24 26

CUT ONE OF PIECE E




60" (150CM)
WITH NAP
ALL SIZES




VIEW 3 - TUNIC AND PANTS

USE PIECES A B C D E F H K L


45" (115CM)
WITH NAP
SIZES 8 10 12 14




45" (115CM)
WITH NAP
SIZES 16 18 20 22 24 26



60" (150CM)
WITH NAP
SIZES 8 10 12 14 16



60" (150CM)
WITH NAP
SIZES 18 20 22 24 26





Congrats!

You've completed your sewing adventure

**SHARE
YOUR** LOOK



Post your pattern and tag us
[@simplicity_creative_group](#) and [#simplicitypatterns](#)
for a chance to be featured on our social media.

Look for more PDF patterns at [simplicity.com](https://www.simplicity.com)

Have a question or need help with your sewing project call us at
1-888-588-2700



Simplicity ©2024 a division of IG Design Group Americas Inc. • Atlanta, GA 30342 USA www.thedesigngroup.com • All Rights Reserved. www.simplicity.com • Made in the U.S.A. Fabriqué aux États-Unis.

To be used for individual private home use only and not for commercial or manufacturing purposes. • A usage privé seulement et non à des fins commerciales ou de production en série. • Para uso privado solamente, no se puede utilizar con propósitos de comercialización o de producción en serie.