

S3088

**Simplicity**



ELAINE HERGL  
DESIGNS

easy-to-sew

Designed and printed in USA.

Shop all the pattern brands you love @

**Simplicity.com**

For customers outside of the U.S. and Canada

**sewdirect.com**

**sewdirect.com.au**

**BODY MEASUREMENTS**

	XS	S	M	L	XL	XXL
<b>Size</b>	0-4	4-6	8-10	12-14	16-18	20-22
<b>Height</b>	5'0-5'3"	5'3-5'7"	5'7-6'0"	6'0-6'3"	6'3-6'6"	6'6-6'9"
<b>Waist</b>	28-32	34-35	36-38	38-42	44-46	48-50
<b>Hip</b>	35-38	38-40	40-42	42-44	46-48	48-50
<b>Plus-Size waist</b>	32-34	34-36	36-38	38-40	40-42	42-44
<b>Back neck to waist</b>	33-35	35-37	37-39	39-41	41-43	43-45

Use the 1 inch (2.54cm) box to ensure you are using rule at 100%

Utilisez la boîte de 2.54 cm pour vous assurer d'utiliser la règle à 100%.

Utilizar un cuadrado de 2.54 cm para asegurarse de estar usando la regla al 100%.

**PICK-A-KNIT® RULE**

FOR THIS PATTERN - 4" (10 cm) OF KNIT FABRIC MUST STRETCH CROSSWISE FROM HERE TO HERE 50% JUSQUE LA 50% HASTA ALLA 50%

POUR CE PATRON - LE JERSEY DOIT S'ETIRER DANS LA LARGEUR DE 4" (10 cm) DEPUIS ICI

PARA ESTE PATRON - LAS MALLAS DEBEN ESTIRARSE A LO ANCHO POR 4" (10 cm) DESDE AQUI

When using the Pick-A-Knit® rule to measure your fabrics stretch capacity, rule must be viewed or printed at 100%.  
 Quand vous utilisez la règle Pick-A-Knit® pour mesurer la capacité d'élasticité des tissus, la règle doit être visible ou imprimée à 100%.  
 Al utilizar la regla Pick-A-Knit® para medir la capacidad de elasticidad de las telas, la regla debe estar visible o impresa al 100%.

Easy

**MISSES' TOPS, PANTS AND APRON DRESSES**

Suggested Fabrics: A,B,C,D in Stretch Knits only such as Cotton Interlock, Jersey, Single Knits. See Pick-A-Knit® Rule. E,F in Broadcloth, Chintz, Cotton Types, Gingham, Lightweight Denim, Lightweight Twill, Linen Types, Madras.

Sizes	XS	S	M	L	XL	XXL		
European	30-32	34-36	38-40	42-44	46-48	50-52		
<b>Top A</b>	60** ¾ 150cm* 0.7	¾ 0.7	1 0.8	1 ¼ 1.1	1 ½ 1.3	1 ¾ 1.4	Yds. m	
<b>Top B</b>	60** 1 150cm* 0.9	1 0.9	1 ¼ 1.1	1 ½ 1.1	1 ¾ 1.3	2 1.4	Yds. m	
<b>Pants C</b>	60** ¾ 150cm* 0.8	1 1.0	1 ¼ 1.0	1 ½ 1.0	1 ¾ 1.3	2 1.3	Yds. m	
<b>Pants D</b>	60** 1 ¼ 150cm* 1.0	1 ½ 1.3	1 ¾ 1.4	2 1.4	2 ¼ 1.8	2 ½ 1.9	Yds. m	
<b>Apron Dress E</b>	45** 2 ¾ 60** 1 ¼ 115cm* 2.2 150cm* 1.5	2 ¾ 1 ¼ 2.2 1.5	2 ¾ 1 ¼ 2.2 1.5	2 ¾ 1 ¼ 2.2 1.6	2 ¾ 1 ¼ 2.2 1.7	2 ¾ 1 ¼ 2.5 1.8	2 ¾ 1 ¼ 2.6 2.1	Yds. "
<b>Apron Dress F</b>	45** 2 ¾ 60** 2 115cm* 2.4 150cm* 1.8	2 ¾ 2 2.4 1.8	2 ¾ 2 2.4 1.8	2 ¾ 2 2.4 1.9	2 ¾ 2 2.6 1.9	3 ¾ 2 2.7 2.2	3 ¾ 2 2.9 2.2	Yds. "

**FINISHED GARMENT MEASUREMENTS**

<b>A,B Bust</b>	33 ½ (85)	35 ½ (90)	39 (99)	43 (109)	47 (119)	51 (130)	Ins. (cm)
<b>A,B Waist</b>	35 ½ (90)	37 ½ (95)	41 (104)	45 (114)	49 (124)	53 (135)	Ins. (cm)
<b>C,D Waist</b>	22 ½ (57)	24 ½ (62)	28 (71)	32 (81)	36 (91)	40 (102)	Ins. (cm)
<b>C,D Hip</b>	31 ½ (80)	33 ½ (85)	37 (94)	41 (104)	45 (114)	49 (124)	Ins. (cm)
<b>Width, lower edge</b>							
<b>Top A,B</b>	36 (91)	38 (97)	41 ½ (105)	45 ½ (116)	49 ½ (126)	53 ½ (136)	Ins. (cm)
<b>Width, each leg</b>							
<b>Pants C</b>	10 ¾ (27)	11 ½ (29)	13 (33)	14 ½ (37)	16 (41)	17 ½ (44)	Ins. (cm)
<b>Pants D</b>	17 ½ (44)	18 ½ (47)	20 ¼ (51)	22 (56)	23 ¾ (60)	25 ½ (66)	Ins. (cm)
<b>Finished back length from base of neck</b>							
<b>Top A,B</b>	18 ½ (47)	19 (48)	19 ½ (50)	20 (51)	20 ½ (52)	21 (53)	Ins. (cm)
<b>Apron Dress E</b>	32 (81)	32 ½ (83)	33 (84)	33 ½ (85)	34 (86)	34 ½ (88)	Ins. (cm)
<b>Apron Dress F</b>	37 ½ (95)	38 (97)	38 ½ (98)	39 (99)	39 ½ (100)	40 (102)	Ins. (cm)
<b>Finished side length from waist</b>							
<b>Pants C</b>	37 ½ (95)	38 (97)	38 ½ (98)	39 (99)	39 ½ (100)	40 (102)	Ins. (cm)
<b>Pants D</b>	25 ½ (65)	26 (66)	26 ½ (67)	27 (69)	27 ½ (70)	28 (71)	Ins. (cm)

\*with nap \*\*without nap




**Simplicity**  
by design


Simplicity ©2024 a division of IG Design Group Americas Inc. • Atlanta, GA 30342 USA www.thedesigngroup.com • All Rights Reserved. www.simplicity.com • Made in the U.S.A. Fabriqué aux États-Unis.  
 To be used for individual private home use only and not for commercial or manufacturing purposes. • A usage privé seulement et non à des fins commerciales ou de production en série. • Para uso privado solamente, no se puede utilizar con propósitos de comercialización o de producción en serie.

# Simplicity

Thank you for purchasing this Simplicity pattern. We made every effort to provide you with a high quality product.



19 PIECES



- 1 FRONT - A,B
- 2 BACK - A,B
- 3 NECKBAND - A,B
- 4 SLEEVE BAND - B
- 5 FRONT - C
- 6 BACK - C
- 7 YOKE FRONT AND BACK - C,D
- 8 FRONT - D
- 9 BACK - D
- 10 FRONT - E,F

- 11 UPPER SIDE FRONT - E,F
- 12 LOWER SIDE FRONT - E,F
- 13 POCKET - E,F
- 14 BACK - E,F
- 15 SIDE BACK - E,F
- 16 STRAP - E,F
- 17 FRONT BAND - E,F
- 18 BACK BAND - E,F
- 19 TIE END - E,F



## General Directions

### The Pattern

- SYMBOLS**
- GRAIN LINE Place on straight grain of fabric parallel to selvage
  - PLACE SOLID LINE on fold of fabric.
  - CENTER FRONT OR BACK of garment.
  - NOTCHES
  - DOTS
  - CUTTING LINE
  - LENGTHEN OR SHORTEN LINES

SEAM ALLOWANCE: 5/8" (1.5cm) unless otherwise stated is included but not printed on MULTI-SIZE PATTERNS. Mark your size with colored felt tip pen. See chart on tissue for how to use MULTI-SIZE PATTERNS.

**ADJUST IF NEEDED**  
Make adjustments before placing pattern on fabric.



When lengthen or shorten lines are not given, make adjustments at lower edge of pattern.

### Cutting/Marking

**BEFORE CUTTING:**  
PRESS pattern pieces with a warm dry iron. PRE-SHRINK fabric by pre-washing washables or steam-pressing non-washables.


CIRCLE your cutting layout.  
PIN pattern to fabric as shown in Cutting Layouts.

- FOR DOUBLE THICKNESS: Fold fabric with RIGHT sides together.
- FOR SINGLE THICKNESS: Place fabric RIGHT side up.
- FOR PILE, SHADED OR ONE WAY DESIGN FABRICS: Use "with nap" layouts

**AFTER CUTTING:**  
Transfer markings to WRONG side of fabric before removing pattern. Use pin and chalk method or dressmaker's tracing paper and wheel.


**To Quick Mark:**

- Snip edge of fabric to mark notches, ends of fold lines and center lines.
- Pin mark dots.




### SPECIAL CUTTING NOTES


★ If layout shows a piece extending past fold, cut out all pieces except piece that extends.




Open out fabric to single thickness. Cut extending piece on RIGHT side of fabric in position shown.




✱ Mark small arrows along both selvages indicating direction of nap or design. Fold fabric crosswise with RIGHT sides together, and cut along fold (a).



Turn one fabric layer around so arrows on both layers go in the same direction. Place RIGHT sides together (b).



## Cutting Layouts




POSITION OF PATTERN PIECES MAY VARY SLIGHTLY ACCORDING TO YOUR PATTERN SIZE


### TOP A

USE PIECES 1 2 3

60" (150CM) WITH NAP SIZES XS S




60" (150CM) WITH NAP SIZES M L XL XXL




### TOP B

USE PIECES 1 2 3 4

60" (150CM) WITH NAP SIZES XS S




60" (150CM) WITH NAP SIZES M L XL XXL




### PANTS C

USE PIECES 5 6 7


60" (150CM) WITH NAP SIZE XS



60" (150CM) WITH NAP SIZES S M L




60" (150CM) WITH NAP SIZES XL XXL




### PANTS D

USE PIECES 7 8 9


60" (150CM) WITH NAP SIZE XS



60" (150CM) WITH NAP SIZES S M L




60" (150CM) WITH NAP SIZES XL XXL




### APRON DRESS E

USE PIECES 10 11 12 13 14 15 16 17 18 19


45" (115CM) WITH NAP SIZES XS S M L




45" (115CM)  
WITH NAP  
SIZES XL XXL



60" (150CM)  
WITH NAP  
SIZES XS S M




60" (150CM)  
WITH NAP  
SIZES L XL XXL




**APRON DRESS F**

USE PIECES 10 11 12 13 14 15 16 17 18 19


45" (115CM)  
WITH NAP  
SIZES XS S M




45" (115CM)  
WITH NAP  
SIZES L XL XXL



60" (150CM)  
WITH NAP  
ALL SIZES



**Sewing Directions**



Read **General Directions** on page 1 before you begin.

Sewing methods in **BOLD TYPE** have Sewing Tutorial Video available. Scan QR CODE to watch videos:

**SLIPSTITCH** – See **Hand Stitching: "how to slip stitch"** video.

**TOPSTITCH** – See **Machine Stitches: "how to topstitch"** video.

**TRIM SEAM** – See **Seams: "how to trim, clip and layer seams"** video.


**PATTERN PIECES WILL BE IDENTIFIED BY NUMBERS THE FIRST TIME THEY ARE USED.**

**STITCH 5/8" (1.5CM) SEAMS WITH RIGHT SIDES TOGETHER UNLESS OTHERWISE STATED.**

SEWING TUTORIALS





Build your skills viewing short, easy-to-follow videos at [simplicity.com/sewingtutorials](http://simplicity.com/sewingtutorials)




**TOP A, B**

**1.** With **RIGHT** sides together and raw edges even, pin **FRONT (1)** to **BACK (2)** at shoulder edges. Stitch.




**2.** Stitch center back seam of **NECKBAND (3)**. Fold band in half, lengthwise, with **WRONG** sides together; press. Pin.

**3.** On **OUTSIDE**, pin band to neck edge, matching centers and notches, placing small dots at shoulder seams and having raw edges even.





**4.** Stitch in a 3/8" (1cm), stretching the band to fit. Stitch again 1/8" (3mm) away from first stitching within the seam allowance. Trim seam close to second stitching. Press seam toward garment, pressing band out.




**5.** Stitch front to back at side edges.

**6. FOR VIEW A** – Press up 3/4" (2cm) on lower edge of sleeve. Stitch a generous 1/2" (1.3cm) from pressed edge, and 1/8" (3mm) above first stitching.




**7. FOR VIEW B** – With **RIGHT** sides together, stitch notched ends of **SLEEVE BAND (4)**.

**8.** Fold sleeve band in half, with **WRONG** sides together and raw edges even; press. Pin.




- 9.** On **OUTSIDE**, pin band to lower edge of sleeve, matching seams and having raw edges even. Stitch. Stitch again 1/4" (6mm) from first stitching within the seam allowance. Trim close to second stitching. Press seam toward sleeve, pressing band out.




- 10. FOR BOTH VIEWS** – Press up 3/4" (2cm) on lower edge of top. Stitch a generous 1/2" (1.3cm) from pressed edge, and 1/8" (3mm) above first stitching.

### PANTS C, D




- 1. FOR VIEW C** – Pin **FRONT** (5) to **BACK** (6) at inner leg edges, matching small dots and notches. Stitch, stretching back edge to fit.




- 2. FOR VIEW D** – Pin **FRONT** (8) to **BACK** (9) at inner leg edges, matching small dots and notches. Stitch, stretching back edge to fit.

- 3. FOR BOTH VIEWS** – Stitch front to back at side edges.




- 4.** With **RIGHT** sides together, insert one leg **INSIDE** the other.




- 5.** Pin center seam, matching inner leg seams and notches. Stitch. To reinforce seam, stitch again over first stitching.

- 6.** With **RIGHT** sides together and raw edges even, pin ends of **YOKE FRONT AND BACK** (7), matching notches. Stitch. Fold yoke in half, lengthwise, with **WRONG** sides together; press. Pin.




- 7.** On **OUTSIDE**, pin yoke to upper edge of pants, matching centers, seams, and notches. Stitch. Stitch again 1/4" (6mm) away from first stitching within the seam allowance. Trim seam close to second stitching. Press seam toward pants, pressing yoke out.




- 8.** Press up 1-1/4" (3.2cm) on lower edge of pant leg. Stitch a generous 1" (2.5cm) from pressed edge, and 1/8" (3mm) below first stitching.


### APRON DRESS C, D



- 1.** With **RIGHT** sides together and raw edges even, pin **POCKET** (13) to **LOWER SIDE FRONT** (12) along upper edge, matching small dots, large dots, and notches. Stitch across upper edge. **TRIM SEAM.**




- 2.** Turn pocket to **INSIDE**; press. ON **OUTSIDE**, **TOPSTITCH** lower side front 1/4" (6mm) from pressed edge.




**3.** With **RIGHT** sides together and raw edges even, pin pocket to **UPPER SIDE FRONT (11)** along lower edge, matching notches. Stitch across lower edge.


**4.** On **OUTSIDE**, pin lower side front to upper side front, matching small dots, large dots, and notches. Baste along side and sides front edges.




**5.** With **RIGHT** sides together and raw edges even, pin side front sections to **FRONT (10)** along side front edges, matching notches. Stitch. Press seams toward front. **TOPSTITCH** front 1/4" (6mm) from seams.




**6.** To edge finish back edge of **BACK (14)**, stitch 1/4" (6mm) from edge, turn under edge along stitching and stitch or zig-zag, or overlock/serge raw edges.



**7.** With **RIGHT** sides together and raw edges even, pin **SIDE BACK (15)** to back along side back edges, matching notches. Stitch. Press seam toward back. **TOPSTITCH** back 1/4" (6mm) from seams.




**8.** Stitch front to back sections at side edges, matching notches. Press seams toward back. **TOPSTITCH** side back 1/4" (6mm) from seams.




**9.** Press up 1-1/4" (3.2cm) hem allowance, turn under raw edge 1/4" (6mm). Press. Stitch hem in place, or if you prefer, **SLIPSTITCH** hem in place.

10




**10.** Stitch FRONT BAND (17) to BACK BAND (18) sections at side edges. Remaining band sections will be used as facings.

11




**11.** Fold STRAP (16) in half, lengthwise, with RIGHT sides together. Stitch long edge. **TRIM SEAM.**

12




**12.** Turn strap; press. Baste raw edges together. On OUTSIDE, **TOPSTITCH** strap 1/4" (6mm) from long edges.

13




**13.** On OUTSIDE, pin ends of strap to upper edge band, matching small and large dots. Baste.

14




**14.** Fold TIE END (19) in half, lengthwise, with RIGHT sides together. Stitch long edge and unmarked end, leaving an opening in long edge for turning. **TRIM SEAM.**

15




**15.** Turn tie ends; press. **SLIPSTITCH** opening closed. On OUTSIDE, **TOPSTITCH** tie 1/4" (6mm) from finished edges.

16




**16.** On OUTSIDE, pin ends of ties to back edges band, matching small and large dots. Baste.

17




**17.** Stitch side edges of front band to back band facing sections in the same manner as band. With RIGHT sides together and raw edges even, pin facing to band (over straps and ties). Stitch upper and back edges. **TRIM SEAM.**

18




**18.** Turn facing to INSIDE; press, pressing out straps and ties. Baste raw edges together.

19




**19.** With RIGHT sides together and raw edges even, pin band to apron, matching centers and notches, turning back edges to OUTSIDE along foldline, (over band). Stitch. **TRIM SEAM.**

20



**20.** Turn back edges to INSIDE along foldline; press, pressing out the band. On OUTSIDE, **TOPSTITCH** band 1/4" (6mm) from seam and finished edges.

21



**21.** On INSIDE. **SLIPSTITCH** back edges in place.



# Congrats!

You've completed your sewing adventure

---

## SHARE YOUR LOOK



Post your pattern and tag us using [#simplicitypatterns](#)  
[@simplicity creative group](#)  
[@simplicitymccallsuk](#)  
[@simplicitymccallsaustralia](#)  
for a chance to be featured on our social media.

Look for more PDF patterns at [simplicity.com](#) or for customers outside the U.S. and Canada visit [sewdirect.com](#) and [sewdirect.com.au](#)

Have a question or need help with your sewing project contact us:  
[Simplicity.com](#)    [Sewdirect.com](#)    [Sewdirect.com.au](#)



Simplicity ©2024 a division of IG Design Group Americas Inc. • Atlanta, GA 30342 USA [www.thedesigngroup.com](#) • All Rights Reserved. [www.simplicity.com](#) • Made in the U.S.A. Fabriqué aux États-Unis.

To be used for individual private home use only and not for commercial or manufacturing purposes. • A usage privé seulement et non à des fins commerciales ou de production en série. • Para uso privado solamente, no se puede utilizar con propósitos de comercialización o de producción en serie.