

1 hour™



easy-to-sew
*Sewing time only.



Very Easy

Très Facile

MISSES' KNIT SKIRTS AND PANTS IN TWO LENGTHS

Suggested Fabrics: Stretch Knits only such as Jersey, Rib Knits, Spandex Blends. See Pick-A-Knit® Rule.

Notions: A, B, C, D: 1¼ yd. (1.2m) of 1" (2.5cm) elastic.

Sizes	4	6	8	10	12	14	16	18	20	22
European	30	32	34	36	38	40	42	44	46	48

BODY MEASUREMENTS: Select pattern size based on body measurements

Bust	29½	30½	31½	32½	34	36	38	40	42	44	Ins.
Waist	22	23	24	25	26½	28	30	32	34	37	"
Hip-9" below waist	31½	32½	33½	34½	36	38	40	42	44	46	"
Back-neck to waist	15¼	15½	15¾	16	16¼	16½	16¾	17	17¼	17½	"

Skirt A	60**	1%	1%	1%	1%	1%	1%	1%	1%	1%	1%	Yds.
Skirt B	60**	1%	1%	1%	1%	1%	1%	1%	1%	1%	1%	Yds.
Pants C	60**	1%	1%	1%	1%	1%	2¼	2¼	2¼	2%	2%	Yds.
Pants D	60**	1%	1%	1%	1%	1%	1%	1%	1%	2		Yds.

FINISHED GARMENT MEASUREMENTS (Includes Design and Wearing Ease)

A,B,C,D Waist	24	25	26	27	28½	30½	32½	34½	36½	38½	Ins.
A,B,C,D Hip	31½	32½	33½	34½	36	38	40	42	44	46	"
Width, each leg											
Pants C	23¼	23½	23¾	24	24½	25	25½	26	26½	27	Ins.
Pants D	21	21¼	21½	21¾	22¼	22½	23¼	23¾	24¼	24½	"
Width, lower edge											
Skirt B	31½	32½	33½	34½	36	38	40	42	44	46	Ins.
Finished back length from waist											
Skirt A	30	30	30	30	30	30	30	30	30	30	Ins.
Skirt B	40	40	40	40	40	40	40	40	40	40	"
Finished side length from waist											
Pants C	40%	40%	40%	41	41½	41½	41½	42	42½	42½	Ins.
Pants D	33%	33%	33%	34	34¼	34¼	34¼	35	35½	35½	"

*with nap **without nap

JUPES ET PANTALON EN TRICOT EN DEUX LONGUEURS POUR JEUNES FEMMES

Tissus Conseillés: Tricot extensibles seulement tels que Tricot Jersey, Tricot à côtes, Mélanges de spandex. Voyez la Règle-Pour-Choisir-Un-Tricot®.

Merci: A, B, C, D: 1.2m d'élastique de 2.5cm.

Tailles	4	6	8	10	12	14	16	18	20	22
Françaises	32	34	36	38	40	42	44	46	48	50
Européen	30	32	34	36	38	40	42	44	46	48

MESURES DU CORPS: Choisissez la taille du patron basée sur les mesures du corps


Poitrine	75	78	80	83	87	92	97	102	107	112	cm
Taille	56	58	61	64	67	71	76	81	87	94	"
Hanches (23cm au-dessous de la taille)											
	80	83	85	88	92	97	102	107	112	117	cm
Dos du cou à la taille	38.5	39.5	40	40.5	41.5	42	42.5	43	44	44	"

Jupe A	150cm*	1.4	1.4	1.5	1.5	1.5	1.5	1.5	1.5	1.6	1.6	m
Jupe B	150cm*	1.2	1.2	1.2	1.2	1.2	1.2	1.2	1.2	1.2	1.2	m
Pantalon C	150cm*	1.3	1.3	1.3	1.3	1.3	2.1	2.1	2.1	2.2	2.4	m
Pantalon D	150cm*	1.1	1.1	1.1	1.1	1.1	1.1	1.2	1.8	1.8	1.8	m

MESURES DES VÊTEMENTS FINI (Motif et aisance de port compris)

A,B,C,D Taille	61	64	66	69	72	77	83	88	93	98	cm
A,B,C,D Hanches	80	83	85	88	91	97	102	107	112	117	"
Largeur, chaque jambe											
Pantalon C	59	60	60	61	62	64	65	66	67	69	cm
Pantalon D	53	54	55	55	57	58	59	60	62	63	"
Largeur à l'ourlet											
Jupe B	80	83	85	88	91	97	102	107	112	117	cm
Longueur finie – dos, taille à l'ourlet											
Jupe A	76	76	76	76	76	76	76	76	76	76	cm
Jupe B	102	102	102	102	102	102	102	102	102	102	"
Longueur finie – côté, taille à l'ourlet											
Pantalon C	102	103	104	104	105	105	106	107	107	108	cm
Pantalon D	84	85	86	86	87	88	88	89	90	90	"

*avec sens **sans sens



Use the 1 inch (2.54cm) box to ensure you are using rule at 100%

Utilisez la boîte de 2.54 cm pour vous assurer d'utiliser la règle à 100%.

Utilizar un cuadrado de 2.54 cm para asegurarse de estar usando la regla al 100%.

PICK-A-KNIT® RULE

FOR THIS PATTERN - 4" (10 cm) OF KNIT FABRIC MUST STRETCH CROSSWISE FROM HERE
POUR CE PATRON - LE JERSEY DOIT S'ÉTIRER DANS LA LARGEUR DE 4" (10 cm) DEPUIS ICI
PARA ESTE PATRON - LAS MALLAS DEBEN ESTIRARSE A LO ANCHO POR 4" (10 cm) DESDE AQUÍ





TO HERE 50%
JUSQUE LA 50%
HASTA ALLA 50%



When using the Pick-A-Knit® rule to measure your fabrics stretch capacity, rule must be viewed or printed at 100%.
Quand vous utilisez la règle Pick-A-Knit® pour mesurer la capacité d'élasticité des tissus, la règle doit être visible ou imprimée à 100%.
Al utilizar la regla Pick-A-Knit® para medir la capacidad de elasticidad de las telas, la regla debe estar visible o impresa al 100%.

Simplicity®

Thank you for purchasing this Simplicity pattern. We made every effort to provide you with a high quality product.



- 1 FRONT AND BACK - A
- 2 LEFT FRONT AND BACK - A
- 3 GUIDE FOR ELASTIC - A,B,C,D
- 4 FRONT AND BACK - B
- 5 FRONT - C,D
- 6 POCKET - C,D
- 7 BACK - C,D

General Directions

The Pattern

- SYMBOLS**
- ↔ GRAIN LINE Place on straight grain of fabric parallel to selvage
 - ⇄ PLACE SOLID LINE on fold of fabric.
 - CENTER FRONT OR BACK of garment.
 - ∇ NOTCHES
 - ○ DOTS
 - CUTTING LINE
 - == LENGTHEN OR SHORTEN LINES

SEAM ALLOWANCE: 5/8" (1.5cm) unless otherwise stated is included but not printed on MULTI-SIZE PATTERNS. Mark your size with colored felt tip pen. See chart on tissue for how to use MULTI-SIZE PATTERNS.

ADJUST IF NEEDED
Make adjustments before placing pattern on fabric.

TO LENGTHEN:
Cut pattern between lengthen or shorten lines. Spread pattern evenly, the amount needed and tape to paper.

TO SHORTEN:
At lengthen or shorten lines, make an even pleat taking up amount needed. Tape in place.

When lengthen or shorten are not given, make adjustments at lower edge of pattern.

Cutting/Marking

BEFORE CUTTING:
PRESS pattern pieces with a warm dry iron. PRE-SHRINK fabric by pre-washing washables or steam-pressing non-washables.

CIRCLE your cutting layout.

PIN pattern to fabric as shown in Cutting Layouts.

• FOR DOUBLE THICKNESS: Fold fabric with RIGHT sides together.

• FOR SINGLE THICKNESS: Place fabric RIGHT side up.

• FOR PILE, SHADED OR ONE WAY DESIGN FABRICS: Use "with nap" layouts

AFTER CUTTING:
Transfer markings to WRONG side of fabric before removing pattern. Use pin and chalk method or dressmaker's tracing paper and wheel.


To Quick Mark:

- Snip edge of fabric to mark notches, ends of fold lines and center lines.
- Pin mark dots.




Sewing

- SEW garment following **Sewing Directions**.
- PIN or machine-baste seams matching notches.
- STITCH 5/8" (1.5 cm) seams unless otherwise stated.
- PRESS seams open unless otherwise indicated clipping when necessary so seams will lie flat.
- TRIM seams to reduce bulk, as shown below.




SPECIAL CUTTING NOTES

★ If layout shows a piece extending past fold, cut out all pieces except piece that extends.




Open out fabric to single thickness. Cut extending piece on RIGHT side of fabric in position shown.




✱ Mark small arrows along both selvages indicating direction of nap or design. Fold fabric crosswise with RIGHT sides together, and cut along fold (a).



Turn one fabric layer around so arrows on both layers go in the same direction. Place RIGHT sides together (b).



Cutting Layouts



POSITION OF PATTERN PIECES MAY VARY SLIGHTLY ACCORDING TO YOUR PATTERN SIZE


ALL VIEWS SIZED FOR STRETCH KNITS ONLY

A,B,C,D: PIECE 3 IS CUT OF ELASTIC

SKIRT A

USE PIECES 1 2


60" (150CM) WITH NAP ALL SIZES



SKIRT B

USE PIECE 4


60" (150CM) WITH NAP ALL SIZES



PANTS C

USE PIECES 5 6 7

60" (150CM) WITH NAP ALL SIZES




PANTS D

USE PIECES 5 6 7

CUT ONE OF PIECE 6

60" (150CM) WITH NAP ALL SIZES




SEWING TUTORIALS



Build your skills viewing short, easy-to-follow videos at [simplicity.com/sewingtutorials](https://www.simplicity.com/sewingtutorials)

FOR OVERLOCK/SERGER

- The Overlock/Serger can be used alone or as a supplement to your conventional sewing machine.
- Overlock sewing machines stitch, trim and finish all in one operation. Therefore, it is VERY important to Check Fit before stitching seams.
- Using matching color thread, baste seams and try garment on. If no adjustments are needed, overlock seams along basting.



Sewing Directions

FABRIC	RIGHT SIDE	WRONG SIDE	INTERFACING	LINING
KEY				

Read **General Directions** on page 1 before you begin.

GLOSSARY OF SEWING METHODS

Sewing methods shown in *ITALICS* are defined below:

NARROW HEM. Press under hem allowance as indicated on tissue pattern. To form narrow hem, tuck under raw edge to meet crease. Press. Stitch hem in place.

SIMPLY THE BEST TECHNIQUES FOR SEWING KNITS

FOR KNITS


- Use a ball point or stretch needle.
- Narrow zig-zag stitch or a stretch stitch.
- To prevent shoulder seams from stretching, pin center of hem tape, clear elastic or twill tape along seam line on front shoulder edges, then stitch the shoulder seams.
- The three thread overlock is ideal for major seams such as shoulder, side, underarm and sleeve seams.
- For stress areas such as crotch seams and armholes, the four thread overlock/safety stitch is best...OR, use a three thread overlock, and stitch along seam with a conventional machine to reinforce.
- The two or three thread overlock stitch is a perfect finish for edges of facings, hems and seam allowances.

SKIRT A

FRONT AND BACK


1. Pin front and back (1) sections together at side seams, matching notches. Stitch.
2. Pin left front and back (2) to lower edge of front and back, matching notches, placing large dot at side seam. Stitch.

3




3. Cut a piece of elastic the length of guide for elastic (3). Transfer all markings with chalk or pencil. Stitch ends together at center back seam.

4




4. On **OUTSIDE**, pin elastic to skirt having upper edges even, matching centers, placing small dots at side seams. Stitch, stretching elastic to fit.

5



5. Turn elastic to **INSIDE**; press. To keep the elastic from rolling to **OUTSIDE**, secure it at the side seams by stitching in the ditch or groove of each seam.


6



6. Make **NARROW HEM** at lower edges, diagonally folding corners, as shown.

SKIRT B







FRONT AND BACK



1. Pin front and back (4) sections together at side seams, matching notches. Stitch, leaving left side open below large dot.

S9751

3 of 3



2. Cut a piece of elastic the length of guide for elastic. Transfer all markings with chalk or pencil. Stitch ends together at center back seam.

3. On **OUTSIDE**, pin elastic to skirt having upper edges even, matching centers, placing small dots at side seams. Stitch, stretching elastic to fit.

4. Turn elastic to **INSIDE**; press. To keep the elastic from rolling to **OUTSIDE**, secure it at the side seams by stitching in the ditch or groove of each seam.

5. Turn up 1 1/4" (3.2cm) hem on lower edge of skirt. Turn 1/4" (6mm) on raw edge of hem to wrong side; press. Stitch close to inner edge of hem. Make **NARROW HEM** at left opening edges, tapering to nothing above large dot, squaring stitching at opening.

PANTS C, D

FRONT AND BACK

1. Press under 1/4" (6mm) on upper edge of pocket (6). Turn upper edge to **OUTSIDE** along fold line, forming facing.

2. Stitch along seam line on raw edges. To ease curved edge of pocket, stitch 1/4" (6mm) **INSIDE** the seam line, using a long machine-stitch. Trim seam allowance in the facing area to 1/4" (6mm).

3. Turn corners **RIGHT** side out, turning facing to the **WRONG** side; press, pressing under raw edges along stitching. Pull up ease stitches to shape the curve. To eliminate bulk, notch out the fullness in the seam allowance along the curves as far as the ease stitches. Stitch facing close to inner edge.






FOR VIEW C

4. On **OUTSIDE**, pin pocket to each front (5) section, matching large dots. Stitch close to side and lower edges.

5. Stitch front to back (7) at side seam, matching notches.

FOR VIEW D

6. On **OUTSIDE**, pin pocket to left front section, matching large dots. Stitch close to side and lower edges.



7. Stitch front to back at side seam, matching notches, leaving open below large dot.

CONTINUE AS FOLLOWS FOR VIEWS C, D

8. Stitch front to back at inner leg seams.

9. With **RIGHT** sides together, insert one leg **INSIDE** the other.

10. With **RIGHT** sides together, pin center seam, matching inner leg seams and notches. Stitch. To reinforce seam, stitch again over first stitching.

11. Cut a piece of elastic the length of guide for elastic. Transfer all markings with chalk or pencil. Stitch ends together at center back seam.

12. On **OUTSIDE**, pin elastic to pants having upper edges even, matching centers, placing small dots at side seams. Stitch, stretching elastic to fit.

13. Turn elastic to **INSIDE**; press. To keep the elastic from rolling to **OUTSIDE**, secure it at seams by stitching in the ditch or groove of each seam.

FOR VIEW C

14. Turn up 1 1/4" (3.2cm) hem on lower edge of pants. Turn 1/4" (6mm) on raw edge of hem to wrong side; press. Stitch close to inner edge of hem.

FOR VIEW D

15. Turn up 1 1/4" (3.2cm) hem on lower edge of pants. Turn 1/4" (6mm) on raw edge of hem to wrong side; press. Stitch close to inner edge of hem. Make **NARROW HEM** at side opening edges, tapering to nothing above large dot, squaring stitching at opening.



Congrats!

You've completed your sewing adventure

**SHARE
YOUR** LOOK



Post your pattern and tag us
@simplicity_creative_group and **#simplicitypatterns**
for a chance to be featured on our social media.

Look for more PDF patterns at **simplicity.com**

Have a question or need help with your sewing project call us at
1-888-588-2700



Simplicity ©2023 a division of IG Design Group Americas Inc. • Atlanta, GA 30342 USA www.thedesigngroup.com • All Rights Reserved. www.simplicity.com • Made in the U.S.A. Fabriqué aux États-Unis.

To be used for individual private home use only and not for commercial or manufacturing purposes. • A usage privé seulement et non à des fins commerciales ou de production en série. • Para uso privado solamente, no se puede utilizar con propósitos de comercialización o de producción en serie.