

S9897

Simplicity®



easy-to-sew

NORRIS DÁNTA FORD



Designed and
printed in USA.

Easy

UNISEX SWEATSHIRT IN TWO LENGTHS

Suggested Fabrics: Stretch Knits only such as Double Knit, Fleece, Ponte, Sweatshirt Fleece, Terry Knits. See Stretch Gauge.

Notions: A,B: Five strips of 6" x 38" (15cm x 97cm) rib knit trim.

Sizes	XS	S	M	L	XL	XXL
	30-32	34-36	38-40	42-44	46-48	50-52

BODY MEASUREMENTS: Select pattern size based on body measurements

Chest	30-32	34-36	38-40	42-44	46-48	50-52	Ins.
Waist	26-27	28-30	32-34	36-39	42-44	46-48	"
Hip	32-34	35-37	39-41	43-45	47-49	51-53	"

Sweatshirt A

60"*	1%	1%	1%	1%	2%	3	Yds.
------	----	----	----	----	----	---	------

Sweatshirt B

60"*	1%	1%	2	2%	2%	3%	Yds.
------	----	----	---	----	----	----	------

FINISHED GARMENT MEASUREMENTS (Includes Design and Wearing Ease)

A,B Bust/Chest	47%	51%	55%	59%	63%	67%	Ins.
A,B Waist	47%	51%	55%	59%	63%	67%	"
Finished back length from base of neck							
Sweatshirt A	26%	27	27%	28	28%	29	Ins.
Sweatshirt B	32%	33	33%	34	34%	35	"

*with nap **without nap

Facile

SWEAT-SHIRT UNISEXE EN DEUX LONGUEURS

Tissus Conseillés: Tricots extensibles tels que Tricot double, Molleton, Ponte, Jersey molletonné pour sweat-shirt, Tricots éponge. Reportez-vous au taux d'élasticité.

Mercurie: A,B : 5 bandes de 15cm x 97cm de galon de tricot à côtes.

Tailles	TP/XS	P/S	M	G/L	TG/XL	TTG/XXL
Fr/ Eur	40-42	44-46	48-50	52-54	56-58	60-62

MESURES DU CORPS: Choisissez la taille du patron basée sur les mesures du corps

Poitrine	76-81	87-92	97-102	107-112	117-122	127-132	cm
Taille	66-69	71-76	81-87	92-99	107-112	117-122	"
Hanches	82-87	89-94	99-104	109-115	119-124	128-135	"

Sweat-shirt A

150cm*	1.6	1.7	1.7	1.7	2.4	2.7	m
--------	-----	-----	-----	-----	-----	-----	---

Sweat-shirt B

150cm*	1.7	1.7	1.8	1.9	2.6	3.1	m
--------	-----	-----	-----	-----	-----	-----	---

MESURES DES VÊTEMENTS FINI (Motif et aisance de port compris)

A,B Poitrine	121	131	141	151	161	171	m
A,B Taille	121	131	141	151	161	171	"
Longueur finie – dos, votre nuque à l'ourlet							
Sweat-shirt A	67	69	70	71	72	74	m
Sweat-shirt B	83	84	85	86	88	89	"

*avec sens **sans sens



A



B

Use the 1 inch (2.54cm) box to ensure you are using rule at 100%

Utilisez la boîte de 2,54 cm pour vous assurer d'utiliser la règle à 100%.

Utilizar un cuadrado de 2.54 cm para asegurarse de estar usando la regla al 100%.

PICK-A-KNIT® RULE

FOR THIS PATTERN - 4" (10 cm) OF KNIT FABRIC MUST STRETCH CROSSWISE FROM HERE
POUR CE PATRON - LE JERSEY DOIT S'ÉTIRER DANS LA LARGEUR DE 4" (10 cm) DEPUIS ICI
PARA ESTE PATRON - LAS MALLAS DEBEN ESTIRARSE A LO ANCHO POR 4" (10 cm) DESDE AQUÍ






TO HERE 50%
JUSQUE LA 50%
HASTA ALLA 50%



When using the Pick-A-Knit® rule to measure your fabrics stretch capacity, rule must be viewed or printed at 100%.
Quand vous utilisez la règle Pick-A-Knit® pour mesurer la capacité d'élasticité des tissus, la règle doit être visible ou imprimée à 100%.
Al utilizar la regla Pick-A-Knit® para medir la capacidad de elasticidad de las telas, la regla debe estar visible o impresa al 100%.

Simplicity®

Thank you for purchasing this Simplicity pattern.
We made every effort to provide you with a high quality product.



- 1 Front-A,B
2 Back-A,B
3 Sleeve-A,B
4 Neckband-A,B
5 Sleeve Band-A,B
6 Hem Band-A,B
7 Pocket-B


www.simplicity.com

info@simplicity.com


1-888-588-2700

General Directions

The Pattern

- SYMBOLS**
- GRAIN LINE Place on straight grain of fabric parallel to selvage
 - PLACE SOLID LINE on fold of fabric.
 - CENTER FRONT OR BACK of garment.
 - NOTCHES
 - DOTS
 - CUTTING LINE
 - LENGTHEN OR SHORTEN LINES

SEAM ALLOWANCE: 5/8" (1.5cm) unless otherwise stated is included but not printed on MULTI-SIZE PATTERNS. Mark your size with colored felt tip pen. See chart on tissue for how to use MULTI-SIZE PATTERNS.

ADJUST IF NEEDED
Make adjustments before placing pattern on fabric.

TO LENGTHEN:
Cut pattern between lengthen or shorten lines. Spread pattern evenly, the amount needed and tape to paper.

TO SHORTEN:
At lengthen or shorten lines, make an even pleat taking up amount needed. Tape in place.

When lengthen or shorten lines are not given, make adjustments at lower edge of pattern.

Cutting/Marking

BEFORE CUTTING:
PRESS pattern pieces with a warm dry iron. PRE-SHRINK fabric by pre-washing washables or steam-pressing non-washables.

CIRCLE your cutting layout.

PIN pattern to fabric as shown in Cutting Layouts.

• FOR DOUBLE THICKNESS: Fold fabric with RIGHT sides together.


• FOR SINGLE THICKNESS: Place fabric RIGHT side up.

• FOR PILE, SHADED OR ONE WAY DESIGN FABRICS: Use "with nap" layouts

AFTER CUTTING:
Transfer markings to WRONG side of fabric before removing pattern. Use pin and chalk method or dressmaker's tracing paper and wheel.


To Quick Mark:

- Snip edge of fabric to mark notches, ends of fold lines and center lines.
- Pin mark dots.




Sewing

- SEW garment following **Sewing Directions**.
- PIN or machine-baste seams matching notches.
- STITCH 5/8" (1.5 cm) seams unless otherwise stated.
- PRESS seams open unless otherwise indicated clipping when necessary so seams will lie flat.
- TRIM seams to reduce bulk, as shown below.




Trim enclosed seams into layers



Trim corners




Clip inner curves




Notch outer curves

SPECIAL CUTTING NOTES


★ If layout shows a piece extending past fold, cut out all pieces except piece that extends.




Open out fabric to single thickness. Cut extending piece on RIGHT side of fabric in position shown.




✱ Mark small arrows along both selvages indicating direction of nap or design. Fold fabric crosswise with RIGHT sides together, and cut along fold (a).



Turn one fabric layer around so arrows on both layers go in the same direction. Place RIGHT sides together (b).



Cutting Layouts




POSITION OF PATTERN PIECES MAY VARY SLIGHTLY ACCORDING TO YOUR PATTERN SIZE

NOTE: See Sewing Directions for cutting Contrat sections.


SWEATSHIRT A

USE PIECES 1 2 3

60" (150CM)
WITH NAP
SIZES XS S M L




60" (150CM)
WITH NAP
SIZES XL XXL




SWEATSHIRT B

USE PIECES 1 2 3 7

60" (150CM)
WITH NAP
SIZES XS S M L




60" (150CM)
WITH NAP
SIZES XL XXL



Sewing Directions

FABRIC
KEY



Read **General Directions** on page 1 before you begin.

SIMPLY THE BEST SEWING TECHNIQUES...

FOR KNITS

- Use a ball point or stretch needle.
- Narrow zig-zag stitch or a stretch stitch.
- To prevent shoulder seams from stretching, pin center of hem tape, clear elastic or twill tape along seam line on front shoulder edges, then stitch the shoulder seams.

FOR OVERLOCK/SERGER

- The Overlock/Serger can be used alone or as a supplement to your conventional sewing machine.
- Overlock sewing machines stitch, trim and finish all in one operation. Therefore, it is VERY important to Check Fit before stitching seams.
- Using matching color thread, baste seams and try garment on. If no adjustments are needed, overlock seams along basting.
- The three thread overlock is ideal for major seams such as shoulder, side, underarm and sleeve seams.
- For stress areas such as crotch seams and armholes, the four thread overlock/safety stitch is best...OR, use a three thread overlock, and stitch along seam with a conventional machine to reinforce.
- The two or three thread overlock stitch is a perfect finish for edges of facings, hems and seam allowances.

PATTERN PIECES WILL BE IDENTIFIED BY NUMBERS THE FIRST TIME THEY ARE USED.


STITCH SEAMS WITH RIGHT SIDES TOGETHER UNLESS OTHERWISE STATED.

SWEATSHIRT A, B

NOTE: View A will be illustrated unless otherwise indicated.

FRONT AND BACK


- 1. VIEW A-** With RIGHT sides together stitch FRONT (1) to BACK (2) at side seams.
- 2. VIEW B-** Pin one POCKET (7) section to FRONT (1) and BACK (2) at each side. Stitch in 1/4" (6mm) seam. Press seams toward pockets.



3. Stitch front and back together at sides, leaving open between large dots. Stitch pocket edges together to side seams. Clip back seam allowances above and below pockets.


4. Turn pockets toward front along seamlines; press.

SLEEVE



5. Stitch underarm in SLEEVE (3) sections.


6. Open out rib knit section if necessary. Pin SLEEVE BAND (5) to rib knit strip, placing center of band along fold on strip. Transfer markings. Cut out two sections.





7. With RIGHT sides together, stitch ends of sleeve band together.


8. With WRONG sides together, sleeve band in half lengthwise; press lightly. Pin raw edges together.

9. Pin band to lower edge of sleeve, matching underarm seams and notches, stretching band to fit. Stitch. Stitch again 1/4" (6mm) away within seam allowances. Trim close to stitching. Press seam toward sleeve, pressing band out.




SCAN QR CODE
FOR A
STEP-BY-STEP
VIDEO TUTORIAL







- 10.** With RIGHT sides together, pin sleeve to armhole edge; baste. Stitch. Stitch again 1/4" (6mm) away within seam allowance. Trim close to stitching. Press seam allowances flat. Turn seam toward sleeve.




- 11.** Open out rib knit section if necessary. Fold strip in half, lengthwise. Pin NECK BAND (4) to rib knit strip, placing center front on pattern piece on folded edge of strip, placing center of band along horizontal fold on strip. Transfer markings.




- 12.** Stitch ends of neck band together.



- 13.** With WRONG sides together, fold neck band in half lengthwise; press lightly. Pin raw edges together.




- 14.** Pin neck band to neck edge, matching small dots, stretching band to fit. Stitch. Stitch again 1/4" (6mm) away in seam allowances. Trim close to stitching. Press seam toward garment, pressing band out.




- 15.** On OUTSIDE, straight or zig-zag stitch garment close to neck seam.


FINISHING




- 16.** Open out rib knit section if necessary. Fold strip in half, lengthwise. Pin HEM BAND (6) to rib knit strip, placing center fold on pattern piece on folded edge of strip, placing center of band along horizontal fold on strip. Transfer markings. Cut out two sections.



- 17.** Stitch ends of hem band sections together at sides.



- 18.** With WRONG sides together, fold neck band in half lengthwise; press lightly. Pin raw edges together.



- 19.** Pin hem band to lower edge of garment, matching small dots, stretching band to fit. Stitch. Stitch again 1/4" (6mm) away in seam allowances. Trim close to stitching. Press seam toward garment, pressing band out.



Congrats!

You've completed your sewing adventure

SHARE YOUR LOOK



Post your pattern and tag us
@simplicity_creative_group and **#simplicitypatterns**
for a chance to be featured on our social media.

Look for more PDF patterns at [simplicity.com](https://www.simplicity.com)

Have a question or need help with your sewing project call us at
1-888-588-2700



Simplicity ©2023 a division of IG Design Group Americas Inc. • Atlanta, GA 30342 USA www.thedesigngroup.com • All Rights Reserved. www.simplicity.com • Made in the U.S.A. Fabriqué aux États-Unis.

To be used for individual private home use only and not for commercial or manufacturing purposes. • A usage privé seulement et non à des fins commerciales ou de production en série. • Para uso privado solamente, no se puede utilizar con propósitos de comercialización o de producción en serie.