

S9929

mi g A DIY & LIFESTYLE BRAND



Scan QR code for a Sew-Along tutorial by sewing celebrity Mimi G.

Simplicity

easy-to-sew

Designed and printed in USA

Easy

Facile

MISSES' AND WOMEN'S LOUNGE SET

Suggested Fabrics: A: Stretch Knits only such as Bamboo, Cotton Knit Blends, ITY, Jacquard, Jersey, Rib Knit. See Pick-A-Knit® Rule. B: Bamboo, Cotton Blends, Double Knit, Interlock, Jersey, Rib Knit, Sweatshirt Fleece, Terry Knit.

Notions: B: 2¼ yds. (2.0m) ¾" (1cm) elastic, 2¼ yds. (2.0m) ½" (1.3cm) twill tape (for ties).

MISSES' SIZES	XS	S	M	L	XL
	4-6	8-10	12-14	16-18	20-22
EUROPEAN	30-32	34-36	38-40	42-44	46-48

BODY MEASUREMENTS: Select pattern size based on body measurements

Bust	29½-30½	31½-32½	34-36	38-40	42-44	Ins.
Waist	22-23	24-25	26½-28	30-32	34-37	"
Hip-9" below waist	31½-32½	33½-34½	36-38	40-42	44-46	"
Back-neck to waist	15¼-15½	15¾-16	16¼-16½	16¾-17	17¼-17½	"

Top A	60**	¾	1	1½	1¾	Yds.
Pants B	60**	2¼	2¼	2¼	2¾	Yds.

WOMEN'S SIZES	1XL	2XL	3XL	4XL	5XL
	20-22W	24-26W	28-30W	32-34W	36-38W
EUROPEAN	48-50	52-54	56-58	60-62	64-66

BODY MEASUREMENTS: Select pattern size based on body measurements

Bust	42-44	46-48	50-52	54-56	58-60	Ins.
Waist	35-37	39-41½	44-46½	49-51½	53-54½	"
Hip-9" below waist	44-46	48-50	52-54	56-58	60-62	"
Back-neck to waist	17¼-17½	17½-17¾	17¾-17¾	18-18½	18½-18¾	"

Top A	60**	1¾	1¾	1¾	1¾	Yds.
Pants B	60**	2¾	2¾	2¾	2¾	Yds.

NOTE: Please refer to the sewing instructions for **FINISHED GARMENT MEASUREMENTS**.

*with nap **without nap

ENSEMBLE DE VÊTEMENTS DE DÉTENTE POUR JEUNES FEMMES ET FEMMES

Tissus Conseillés: A: Tricot extensibles seulement tels que Bamboo, Mélanges de tricot de coton, Tricot interlock en fil retors, Jacquard, Jersey, Tricot à côtes. Reportez-vous à la règle Pick-A-Knit®. B: Bambou, Cottonnades, Tricot double, Interlock, Jersey, Tricot à côtes, Jersey molletonné pour sweat-shirt, Tricot éponge.

Mercerie: B: 2.0m de élastique de 1cm, 2.0m de talonnette de coton de 1.3cm (pour attaches).

TAILLES - FR (J. FEMMES)	TP	P	M	G	TG
	32-34	36-38	40-42	44-46	48-50
	XS	S	M	L	XL
TAILLES - EURO	30-32	34-36	38-40	42-44	46-48

MESURES DU CORPS: Choisissez la taille du patron basée sur les mesures du corps

Poitrine	75-77	80-83	87-92	97-102	107-112	cm
Taille	56-58	61-64	67-71	76-81	87-94	"
Hanches (23cm au-dessous de la taille)						
	80-83	85-88	92-97	102-107	112-117	cm
Dos du cou à la taille	44-44	44.5-45	45-45.5	46-46	46.5-47	"
Haut A	150cm*	0.8	0.9	1.0	1.1	m
Pantalons B	150cm*	2.1	2.1	2.1	2.2	m

TAILLES - FR (FEMMES)	1TG	2TG	3TG	4TG	5TG
	48-50	52-54	56-58	60-62	64-66
	1XL	2XL	3XL	4XL	5XL
TAILLES - EURO	46-48	50-52	54-56	58-60	62-64

MESURES DU CORPS: Choisissez la taille du patron basée sur les mesures du corps

Poitrine	107-112	117-122	127-132	137-142	147-152	cm
Taille	89-94	99-105	112-118	124-131	135-138	"
Hanches (23cm au-dessous de la taille)						
	112-117	122-127	132-137	142-147	152-157	cm
Dos du cou à la taille	39-39.5	40-40.5	41.5-42	42.5-43	44-44.5	"
Haut A	150cm*	1.3	1.3	1.4	1.5	m
Pantalons B	150cm*	2.4	2.4	2.5	2.5	m

NOTE: S'il vous plaît, reportez-vous aux instructions de couture pour les **MESURES DU VÊTEMENTS FINI**.

*avec sens **sans sens



A



B

Use the 1 inch (2.54cm) box to ensure you are using rule at 100%

Utilisez la boîte de 2.54 cm pour vous assurer d'utiliser la règle à 100%.

Utilizar un cuadrado de 2.54 cm para asegurarse de estar usando la regla al 100%.

PICK-A-KNIT® RULE

**FOR THIS PATTERN - 4" (10 cm) OF KNIT FABRIC MUST STRETCH CROSSWISE FROM HERE
POUR CE PATRON - LE JERSEY DOIT S'ÉTIRER DANS LA LARGEUR DE 4" (10 cm) DEPUIS ICI
PARA ESTE PATRON - LAS MALLAS DEBEN ESTIRARSE A LO ANCHO POR 4" (10 cm) DESDE AQUÍ**



**TO HERE 50%
JUSQUE LA 50%
HASTA ALLA 50%**





When using the Pick-A-Knit® rule to measure your fabrics stretch capacity, rule must be viewed or printed at 100%.

Quand vous utilisez la règle Pick-A-Knit® pour mesurer la capacité d'élasticité des tissus, la règle doit être visible ou imprimée à 100%.


Al utilizar la regla Pick-A-Knit® para medir la capacidad de elasticidad de las telas, la regla debe estar visible o impresa al 100%.

Simplicity®

Thank you for purchasing this Simplicity pattern.
We made every effort to provide you with a high quality product.



miG A DIY & LIFESTYLE BRAND



- 1 FRONT-A
2 BACK-A
3 BACK NECK FACING-A
4 ARMHOLE BAND-A
5 LOWER BAND-A
6 FRONT-B
7 POCKET-B
8 POCKET FACING-B
9 BACK-B
10 GUSSET-B
11 CASING-B
12 ELASTIC GUIDE FOR WAIST-B


www.simplicity.com

info@simplicity.com


1-888-588-2700

General Directions

The Pattern

- SYMBOLS**
- ↔ GRAIN LINE Place on straight grain of fabric parallel to selvage
 - PLACE SOLID LINE on fold of fabric.
 - - - CENTER FRONT OR BACK of garment.
 - ▽ NOTCHES
 - DOTS
 - CUTTING LINE
 - LENGTHEN OR SHORTEN LINES

SEAM ALLOWANCE: 5/8" (1.5cm) unless otherwise stated is included but not printed on MULTI-SIZE PATTERNS. Mark your size with colored felt tip pen. See chart on tissue for how to use MULTI-SIZE PATTERNS.

ADJUST IF NEEDED

Make adjustments before placing pattern on fabric.


TO LENGTHEN:
Cut pattern between lengthen or shorten lines. Spread pattern evenly, the amount needed and tape to paper.

TO SHORTEN:
At lengthen or shorten lines, make an even pleat taking up amount needed. Tape in place.


When lengthen or shorten lines are not given, make adjustments at lower edge of pattern.

Sewing

- SEW garment following **Sewing Directions**.
- PIN or machine-baste seams matching notches.
- STITCH 5/8" (1.5 cm) seams unless otherwise stated.
- PRESS seams open unless otherwise indicated clipping when necessary so seams will lie flat.
- TRIM seams to reduce bulk, as shown below.




Trim enclosed seams into layers



Trim corners



Clip inner curves



Notch outer curves

Cutting/Marking

BEFORE CUTTING:

PRESS pattern pieces with a warm dry iron. PRE-SHRINK fabric by pre-washing washables or steam-pressing non-washables.

CIRCLE your cutting layout.

PIN pattern to fabric as shown in Cutting Layouts.


- FOR DOUBLE THICKNESS: Fold fabric with RIGHT sides together.
- FOR SINGLE THICKNESS: Place fabric RIGHT side up.
- FOR PILE, SHADED OR ONE WAY DESIGN FABRICS: Use "with nap" layouts

AFTER CUTTING:

Transfer markings to WRONG side of fabric before removing pattern. Use pin and chalk method or dressmaker's tracing paper and wheel.

To Quick Mark:

- Snip edge of fabric to mark notches, ends of fold lines and center lines.
- Pin mark dots.





SPECIAL CUTTING NOTES

★ If layout shows a piece extending past fold, cut out all pieces except piece that extends.


Open out fabric to single thickness. Cut extending piece on RIGHT side of fabric in position shown.

✱ Mark small arrows along both selvages indicating direction of nap or design. Fold fabric crosswise with RIGHT sides together, and cut along fold (a).

Turn one fabric layer around so arrows on both layers go in the same direction. Place RIGHT sides together (b).



Cutting Layouts



POSITION OF PATTERN PIECES MAY VARY SLIGHTLY ACCORDING TO YOUR PATTERN SIZE

MISSES' SIZES	XS	S	M	L	XL
EUROPEAN	4-6 30-32	8-10 34-36	12-14 38-40	16-18 42-44	20-22 46-48

FINISHED GARMENT MEASUREMENTS (Includes Design and Wearing Ease)					
B Hip	38½	40½	44½	48½	52½
Width, each leg					Ins.
Pants B	34	34½	35½	36½	37½
Finished side length from waist					Ins.
Pants B	35½	36	36½	37	37½


WOMEN'S SIZES	1XL	2XL	3XL	4XL	5XL
EUROPEAN	20-22W 48-50	24-26W 52-54	28-30W 56-58	32-34W 60-62	36-38W 64-66

FINISHED GARMENT MEASUREMENTS (Includes Design and Wearing Ease)					
B Hip	53	57	61	65	69
Width, each leg					Ins.
Pants B	43½	45	47	49	51
Finished side length from waist					Ins.
Pants B	38½	39	39½	40	40½

TOP A

USE PIECES 1 2 3 4 5



60" (150CM)
WITH NAP
SIZES XS S M L XL



PANTS B

USE PIECES 6 7 8 9 10 11

60" (150CM)
WITH NAP
SIZES XS S M XL





Sewing Directions

FABRIC KEY RIGHT SIDE WRONG SIDE INTERFACING LINING FINISHING

Read **General Directions** on page 1 before you begin.

SIMPLY THE BEST SEWING TECHNIQUES FOR KNITS

- Use a ball point or stretch needle.
- Narrow zig-zag stitch or a stretch stitch.
- To prevent shoulder seams from stretching, pin center of hem tape, clear elastic or twill tape along seam line on front shoulder edges, then stitch the shoulder seams.



FOR OVERLOCK/SERGER

- The Overlock/Serger can be used alone or as a supplement to your conventional sewing machine.
- Overlock sewing machines stitch, trim and finish all in one operation. Therefore, it is important to check fit before stitching seams.
- Using matching color thread, baste seams and try garment on. If no adjustments are needed, overlock seams along basting.
- The three thread overlock is ideal for major seams such as shoulder, side, underarm and sleeve seams.
- For stress areas such as crotch seams and armholes, the four thread overlock/safety stitch is best...OR, use a three thread overlock, and stitch along seam with a conventional machine to reinforce.
- The two or three thread overlock stitch is a perfect finish for edges of facings, hems and seam allowances.

GLOSSARY OF SEWING METHODS

Sewing methods shown in **ITALICS** are defined below:

EDGESTITCH – Stitch close to finished edge or seam.

NARROW HEM – Press under hem allowance as indicated on tissue pattern. To form narrow hem, tuck under raw edge to meet crease. Press. Stitch hem in place.

TOPSTITCH – On outside, stitch 1/4" (6mm) from edge, seam or previous stitching, using presser foot as guide, or stitch as indicated in instructions.









UNDERSTITCH – Press facing and seam away from garment, stitching through facing and seam allowances close to seam.

PATTERN PIECES WILL BE IDENTIFIED BY NUMBERS THE FIRST TIME THEY ARE USED.

STITCH 5/8" (1.5CM) SEAMS WITH RIGHT SIDES TOGETHER UNLESS OTHERWISE STATED.

TOP A

1. To make pleats on **FRONT (1)**, on inside, bring broken lines together. Stitch along broken lines. Press pleat toward armhole. Baste raw edges together.



2. Fold **BACK NECK FACING (3)** in half with wrong sides together; pin. On outside, pin facing to **BACK (2)**, matching centers, small dots, and notches. Stitch in a 3/8" (1cm) seam, stretching the band to fit. Trim seam.

3. **UNDERSTITCH** the facing. Turn facing to inside; press. **EDGESTITCH** close to inner edge, stretching the facing to fit.

4. With right sides together and raw edges even, pin front to back at shoulder edges, matching small dots. baste.










5. Fold front facing to inside along foldline (over back). Stitch shoulder edges through all thicknesses. Press seam toward front.

6. Stitch front to back at side edges from lower edge to small dot, back-stitching at dot to reinforce the seam. Clip to dot.

7. Fold **ARMHOLE BAND (4)** in half, lengthwise, with wrong sides together, matching small dots and notches; press. Pin.

8. Lap ends of armhole band front over back, matching small dots, having raw edges even; pin. This is the outside of your band. Machine-baste ends of armhole band together along seam line, through all thicknesses. Machine-baste ends of armhole band through center where folded edges meet, as shown. This is the "side seam".

9. Turn top wrong side out. With right sides together, pin band to armhole edge, matching small dots and notches, placing inner small dots at shoulder seams, having raw edges even. Smooth out fullness at point of "V" and spread unstitched seamlines of side seam apart, placing a pin 1" (2.5cm) each side of clip. Baste along seam line between pins. With band against the machine and top toward you, stitch along seam line, stretching band to fit, pivoting with needle in fabric at side seam. To reinforce seam at side seam, stitch again over first stitching. Stitch again 1/4" (6mm) from first stitching within the seam allowance.



10. Trim seam close to second stitching. Remove basting. Press seam toward top, pressing band out.

11. Stitch ends of LOWER BAND (5). Fold band in half, lengthwise, with wrong sides together; press. Pin.

12. On outside, pin band to lower edge of top, matching centers and notches, placing small dots at right side seam, and having raw edges even.

13. Stitch, stretching the band to fit. Stitch again 1/4" (6mm) away from first stitching within the seam allowance. Trim seam close to second stitching. Press seam toward top, pressing band out.

PANTS B

NOTE: To prepare drawstring for pants, cut a piece of twill tape the length of your waist measurement, plus 36" (92cm).


1. Pin POCKET FACING (8) to POCKET (7) with wrong sides together, matching large dots and notches. Stitch along stitching lines. (Edges of pocket and facing are left raw.) Baste along seamline.

2. Stitch remaining edge of pocket along seamline. Press under seam allowance along stitching.


3. On outside, pin pressed edge of pocket to FRONT (6) along placement line. **EDGESTITCH** pressed edge. Baste raw edges together.

4. Stitch center front edges of front. **EDGESTITCH** both sides of seam.


5. With right sides together and raw edges even, pin gusset (10) to inner leg edges of front, matching small dots and notches. Stitch. Press seam toward front.



6. On outside, **EDGESTITCH** and **TOPSTITCH** front 1/4" (6mm) from seam.




7. Stitch center back edges of BACK (9). **EDGESTITCH** both sides of seam.




8. With right sides together and raw edges even, pin gusset to inner leg edges of back, matching small dots and notches. Stitch. Press seam toward back.

S9929


4 of 4




9. On outside, **EDGE**STITCH and **TOP**STITCH back 1/4" (6mm) from seam.




10. Stitch front to back at side edges. Press seam toward back. On outside, **EDGE**STITCH and **TOP**STITCH back 1/4" (6mm) from seam.




11. Apply a remnant of fusible interfacing to CASING (11) large enough to cover buttonhole area. Fuse in place following manufacturer's directions. On outside, make buttonholes in casing at markings. This is the front of the casing.




12. With right sides together, stitch center back seam of casing, leaving an opening between small dots, as shown. Back-stitch at small dots to reinforce seam. Press seam open.




13. Fold casing in half, lengthwise, with wrong sides together, having raw edges even. Baste raw edges together. The side with the opening is the underside of the casing.




14. With the underside of casing facing you, pin casing to pants, matching centers and notches, placing small dots at side seams. Stitch along seam line. Stitch again 1/4" (6mm) from first stitching within seam allowance. Trim close to second stitching.




15. Press seam toward pants, pressing casing out. Stitch along stitching lines to form separate casings.



16. Using ELASTIC GUIDE FOR WAIST (12), cut two pieces of elastic. Insert elastic through upper and lower openings in casing, working elastic through rows at same time. This eliminates that tug-of-war that can happen when trying to pull that last piece of elastic through an already bunched up casing. Overlap ends and hold with safety pins. Try on pants and adjust to fit. Stitch ends of elastic together securely.



17. Slip-stitch opening edges of each casing together. Distribute fullness evenly.
TIP-To secure elastic so it won't twist in wearing, stitch through all thicknesses of casing in the groove of each seam.



18. Thread twill tape drawstring through buttonholes. Press under 1" (2.5cm) on raw edges of drawstring. Turn under raw edge to meet crease. Stitch close to inner pressed edge.
Tie in front when wearing.



19. Make a **NARROW HEM** on lower edge of pant legs, however if you prefer, leave lower edge unhemmed.



Congrats!

You've completed your sewing adventure

SHARE YOUR LOOK



Post your pattern and tag us
@simplicity_creative_group and **#simplicitypatterns**
for a chance to be featured on our social media.

Look for more PDF patterns at [simplicity.com](https://www.simplicity.com)

Have a question or need help with your sewing project call us at
1-888-588-2700



Simplicity ©2024 a division of IG Design Group Americas Inc. • Atlanta, GA 30342 USA www.thedesigngroup.com • All Rights Reserved. www.simplicity.com • Made in the U.S.A. Fabriqué aux États-Unis.

To be used for individual private home use only and not for commercial or manufacturing purposes. • A usage privé seulement et non à des fins commerciales ou de production en série. • Para uso privado solamente, no se puede utilizar con propósitos de comercialización o de producción en serie.